# "pydvbcss - a library implementing DVB protocols for Companion Screen Synchronisation

Release 0.4.1-release

**British Broadcasting Corporation** 

# Contents

1	Run the examples	3
2	DVB CSS Protocol modules	9
3	Clocks, Time and Scheduling modules	55
4	Internal implementation details	95
5	Getting started	101
6	State of implementation	103
7	Upgrading from previous versions	105
8	License and Contributing	107
9	Contact and discuss	109
Ру	thon Module Index	111

DVB protocols for synchronisation between TV Devices and Companion Screen Applications.

Release 0.4.1-release

Licence Apache License v2.0.

**Source** https://github.com/BBC/pydvbcss/tree/0.4.1/

 $\label{lem:background} \begin{tabular}{ll} How to install $https://github.com/BBC/pydvbcss/tree/0.4.1/README.md \\ Changelog $https://github.com/BBC/pydvbcss/tree/0.4.1/CHANGELOG.md \\ \end{tabular}$ 

Contents 1

"pydvbcss - a library implementing DVB protocols for Companion Screen Synchronisation, Release 0.4.1-release

2 Contents

# CHAPTER 1

# Run the examples

The code in the *examples* directory demonstrates how to create and control servers and clients for all three protocols: CSS-CII, CSS-TS and CSS-WC.

- WallClockServer.py and WallClockClient.py
- CIIServer.py and CIIClient.py
- TSServer.py and TSClient.py
- TVDevice.py

There are instructions below on how to run the examples and see them interact with each other.

See the sources here: on github

# WallClockServer.py and WallClockClient.py

# **Get started**

The WallClockServer and WallClockClient examples use the library to implement a simple server and client for the CSS-WC protocol.

First start the server, specifying the host and IP to listen on:

```
$ python examples/WallClockServer.py 127.0.0.1 6677
```

Leave it running in the background and start a client, telling it where to connect to the server:

```
$ python examples/WallClockClient.py 127.0.0.1 6677
```

# "pydvbcss - a library implementing DVB protocols for Companion Screen Synchronisation, Release 0.4.1-release

**Note:** The wall clock protocol is connectionless (it uses UDP) This means the client will not report an error if you enter the wrong IP address or port number.

Watch the "dispersion" values which indicate how much margin for error there is in the client's wall clock estimate. If the value is very large, this means it is not receiving responses from the server.

# How they work

# WallClockServer.py [source]

It works by instantiating a WallClockServer object and providing that object with a clock object to be used as the Wall Clock that is to be served.

At the command line you can override default options for the ip address and port the server binds to; the maximum frequency error it reports and whether it sends "follow-up" responses to requests.

Use the --help command line option for usage information.

# WallClockClient.py [source]

It works by instantiating a <code>WallClockClient</code> object and plugs into that object a <code>LowestDispersionCandidate</code> algorithm object that adjusts a <code>TunableClock</code> representing the Wall Clock.

At the command line you must specify the host and port of the Wall Clock server. Default options can be overridden for the IP address and port that the client listens on.

Use the --help command line option for usage information.

# CIIServer.py and CIIClient.py

# **Get started**

The CIIServer and CIIClient examples implement the CSS-CII protocol, with the server sharing some pretend CII status information with the client.

First start the server:

```
$ python examples/CIIServer.py
```

The server listens on 127.0.0.1 on port 7681 and accepts WebSocket connections to ws://<ip>:<port>/cii.

Leave it running in the background and connect using the client and see how the CII data is pushed by the server whenever it changes:

\$ python examples/CIIClient.py ws:/127.0.0.1:7681/cii

# How they work

# CIIServer.py [source]

It works by setting up a web server and the ws4py plug-in for cherrypy that provides WebSockets support. It then instantiates a CIIServer and mounts it into the cherrypy server at the URL resource path "/cii".

While the server is running, it pretends to be hopping between a few different broadcast channels every 7 seconds, with a 2 second "transitioning" period on each hop.

This is an artificially simple example and does not provide values for most properties of the CII message - such as a MRS URL, or any URLs for a WC or TS endpoints.

It does not do any media presentation, but just provides a CSS-CII server with some pretend data.

This server, by default, serves on port 7681 and provides a CSS-CII service at the URL resource path /cii. It can therefore be connected to using the WebSocket URL "ws://<host>:7681/cii" e.g. "ws://127.0.0.1:7681/cii". Command line options can be used to override these defaults and to reduce the amount of logging output.

Use the --help command line option for more detailed usage information.

# CIIServer.py [source]

It works by instantiating a CIIClient and attaching handler functions to be notified of when connection and disconnection occurs and of changes to the CII information being pushed from the server.

At the command line you must specify:

• the WebSocket URL of the CSS-CII server, in the form ws://<host>:<port>/<path>

Command line options can be used to reduce the amount of logging output.

Use the --help command line option for usage information.

# TSServer.py and TSClient.py

#### **Get started**

The *TServer* and *TSClient* examples implement the *CSS-TS* protocol, with the server pretending to have a few different timelines for a DVB broadcast service (where the content ID is a DVB URL).

First start the server:

```
$ python examples/TSServer.py
```

The server listens on 127.0.0.1 on port 7681 and accepts WebSocket connections to ws://<ip>:<port>/ts. It also includes a wall clock server, also on 127.0.0.1 on port 6677.

Leave it running in the background and connect using the client and see how the client is able to synchronise and periodically print an estimate of the timeline position (converted to units of seconds):

```
$ python examples/TSClient.py ws://127.0.0.1:7681/ts udp://127.0.0.1:6677 "dvb://"
→"urn:dvb:css:timeline:pts" 90000
```

Here we have told it to request a timeline for whatever content the server thinks it is showing provided that the content ID begins with "dvb://". Assuming that matches, then the timeline is to be a PTS timeline, which ticks at 90kHz (the standard rate of PTS in an MPEG transport stream).

# How they work

# TSServer.py [source]

It works by setting up a web server and the ws4py plug-in for cherrypy that provides WebSockets support. It then instantiates a TSServer and mounts it into the cherrypy server at the URL resource path "/ts". It also includes a wall clock server.

It does not play any media, but instead serves an imaginary set of timelines.

It creates *clock* objects to represent timelines and the wall clock. SimpleClockTimelineSource objects are used to interface the clocks as sources of timelines to the TS server object.

It has a hardcoded DVB URL as the content ID (displayed when you start it running) and provides the following timelines:

- "urn:dvb:css:timeline:pts" ... a PTS timeline
- "urn:dvb:css:timelime:temi:1:1" ... a TEMI timeline ticking at 1kHz
- "urn:dvb:css:timelime:temi:1:5" ... a TEMI timeline ticking at 1kHz, that toggles availability every 10 seconds
- "urn:dvb:css:timelime:temi:1:2" ... the same, but it takes 10 seconds for the server to begin providing this timeline after a client first requests it
- "urn:pydvbcss:sporadic" ... a meaningless timeline whose availability toggles every 10 seconds.

The PTS and TEMI timelines both pause periodically and have their timing tweaked by a fraction of a second. The "sporadic" timeline shows how the protocol supports having timelines appear (become available) and disappear (become unavailable) while a client is connected.

By default, this server serves at 127.0.0.1 on port 7681 and provides a CSS-TS service at the URL ws://127.0.0.1:7681/ts. It also provides a wall clock server bound to 0.0.0.0 on UDP port 6677. Command line options can be used to override these defaults and to reduce the amount of logging output.

Use the --help command line option for more detailed usage information.

## TSClient.py [source]

It works by implementing *both* a wall clock client and a CSS-TS client. A *TSClientClockController* object is instantiated and provided with a *CorrelatedClock* object to represent the synchronisation timeline. The controller adjusts the clock object to match the timeline information coming from the server.

At the command line you must specify:

- the WebSocket URL of the CSS-TS server, in the form ws://<host>:<port>/<path>
- a *udp://<host>:<port>* format URL for the Wall Clock server
- The content ID stem and timeline selector to be used when requesting the timeline
- The tick rate of the timeline.

Default options can be overridden for the IP address and port that the Wall Clock client binds to and to reduce the amount of logging output.

Use the --help command line option for usage information.

# TVDevice.py

# **Get started**

This is a very simple example of a server running all three protocols (CSS-WC, CSS-TS and CSS-CII). It pretends to be showing a DVB broadcast service and able to provide a PTS or TEMI timeline for it.

First start the server:

```
$ python examples/TVDevice.py
```

While we leave it running in the background, we can try to interact with it using the various example clients described above.

By default it provides a wall clock server on 127.0.0.1 port 6677

```
$ python examples/WallClockClient.py 127.0.0.1 6677
```

... and a CSS-CII server that can be reached at ws://127.0.0.1:7681/cii

```
$ python examples/CIIClient.py ws:/127.0.0.1:7681/cii
```

... and a CSS-TS server that can be reached at ws://127.0.0.1:7681/ts

```
$ python examples/TSClient.py ws://127.0.0.1:7681/ts udp://127.0.0.1:6677 "dvb://"
→"urn:dvb:css:timeline:temi:1:1" 1000
```

# How it works

## TVDevice.py [source]

This example works by setting up a web server and the ws4py plug-in for cherrypy that provides WebSockets support. It then instantiates a TSServer and CIIServer and mounts it into the cherrypy server. It also includes a wall clock server.

It does not play any media, but instead serves an imaginary set of timelines and pretends to be presenting a broadcast service

It creates <code>clock</code> objects to represent timelines and the wall clock. SimpleClockTimelineSource objects are used to interface the clocks as sources of timelines to the TS server object.

It has a hardcoded DVB URL as the content ID (displayed when you start it running) and provides the following timelines:

- urn:dvb:css:timeline:pts ... a PTS timeline
- urn:dvb:css:timelime:temi:1:1 ... a TEMI timeline ticking at 1kHz that toggles availability every 30 seconds

The PTS and TEMI timelines both start ticking up from zero the moment the server starts.

By default, this server serves at 127.0.0.1 on port 7681 and provides a CSS-CII service at the URL ws://127.0.0.1:7681/cii and a CSS-TS service at the URL ws://127.0.0.1:7681/ts. It also provides a wall clock server bound to 0.0.0.0 on UDP port 6677. Command line options can be used to override these defaults and to reduce the amount of logging output.

Use the --help command line option for more detailed usage information.

1.4. TVDevice.py 7

9 U.4.1-release		r Companion S	

# CHAPTER 2

# **DVB CSS Protocol modules**

Module: dvbcss.protocol

The <code>dvbcss.protocol</code> module contains classes to implement the CSS-CII, CSS-TS and CSS-WC protocols. For each protocol there are objects to represent the messages that flow across the protocols and classes that implement clients and servers for the protocols.

# **CSS-CII** protocol

# **CSS-CII Protocol introduction**

Here is a quick introduction to the CSS-CII protocol. For full details, refer to the DVB specification ETSI 103 286 part 2.

The CSS-CII protocol is for sharing the server's (e.g. TV's) current "Content Identifier and other Information" (yes really!) with the client (e.g. companion). It also includes the URL of the CSS-TS and CSS-WC servers so the client knows where to find them.

CII comprises a set of defined properties. The server pushes state update messages containing some or all properties (at minimum those that have changed). How often these messages are pushed and which properties are included are up to the server.

It is a WebSockets based protocol and messages are in JSON format.

- Sequence of interaction
- CII message properties

#### Sequence of interaction

The client is assumed to already know the WebSocket URL for the CSS-CII server (for example: because the TV chooses to advertise it via a network service discovery mechanism).

- 1. The client connects to the CSS-TS server. Either this is refused via an HTTP status code response, or it is accepted.
- 2. The server immediately responds with a first CII state update message. This contains (at minimum) all properties whose values are not *null*.
- 3. The server can re-send the CII state update message as often as it wishes. At minimum it will do so when one or more of the properties have changed value. The server will, at minimum, include the properties that have changed, but could also include others in the message.

This protocol is a state update mechanism. The client is locally mirroring the state of the TV by remembering the most recent values received for each of the properties.

At the start, the client assumes all properties have the value *null*. Then, when a message is received the client updates its mirror of the TV state:

- If a property is included in the message (even if its value is *null*), then this is the new value for that property.
- If a property is not included in the message, then its value has not changed.

Any messages sent by the client are ignored by the server.

# **CII message properties**

Every message sent by the server is a CII message and consists of a single JSON object with zero, one, more or all of the following properties:

- protocolVersion currently "1.1" and must be included in the first message sent by the server after the client connects.
- contentId a URI representing the ID of the content being presented by the server. This will be a variant on a DVB URL ("dvb://") for DVB broadcast services, or the URL of the MPD for MPEG DASH streams.
- contentIdStatus whether the content Id is in its "final" form or whether it is a "partial" version until full information is available. For example: a DVB broadcast content ID might not include some elements until the TV detects certain metadata in the broadcast stream which can take a few seconds.
- presentationStatus Primarily, whether presentation of the content is "okay", "transitioning" from one piece of content to the next, or in a "fault" condition. This can be extended by suffixing space separated additional terms after the primary term.
- mrsUrl The URL of an MRS server.
- tsUrl The WebSockets URL of the CSS-TS server that a client should use if it wants to do Timeline Synchronisation.
- wcUrl The UDP URL ("udp://<host>:<port") of the CSS-WC server.
- teUrl The WebSockets URL of the CSS-TE server that a client should use if it wants to receive Trigger Events.
- ullet timelines a list of zero, one or more timelines that the TV believes to be available for synchronising to.
- private Extension mechanism to carry additional private data.

An example CII message:

Another example where the contentId has changed, due to a channel change. The server has chosen to omit properties that have not changed since the previous message:

# **CSS-CII Message objects**

Module: dvbcss.protocol.cii

Examples
Classes
CII Message
Timeline Option

A CII object represents a CII message sent from server to client via the CSS-CII protocol.

A TimelineOption object describes a timeline selector and the tick rate of the timeline if that selector is used to request a timeline from the CSS-TS server. It is carried in a list in the timelines property of a CII message.

# **Examples**

CII messages:

```
>>> from dvbcss.protocol.cii import CII
>>> from dvbcss.protocol import OMIT

>>> jsonCiiMessage = \"""\
... { "protocolVersion":"1.1",
... "contentId":"dvb://1234.5678.01ab",
```

TimelineOption within CII messages:

```
>>> from dvbcss.protocol.cii import CII, TimelineOption
>>> t1 = TimelineOption(timelineSelector="urn:dvb:css:timeline:pts", unitsPerTick=1, unitsPerSecond=90000)
>>> t2 = TimelineOption(timelineSelector="urn:dvb:css:timeline:temi:1:1", unitsPerTick=1, unitsPerSecond=1000)
>>> print t1.timelineSelector, t1.unitsPerTick, t1.unitsPerSecond, t1.accuracy urn:dvb:css:timeline:pts 1 90000 OMIT
```

#### **Classes**

#### **CII Message**

```
class dvbcss.protocol.cii.CII (**kwargs)
   Object representing a CII message used in the CSS-CII protocol.
```

Initialisation takes the following parameters, all of which are optional keyword arguments that default to  $\mathit{OMIT}$ :

#### **Parameters**

- protocolVersion (OMIT or "1.1") The protocol version being used by the server.
- mrsUrl (OMIT or str) The URL of an MRS server known to the server.

- contentId (OMIT or str) Content identifier URI.
- contentIdStatus (OMIT or "partial" or "final") Content identifier status.
- presentationStatus (OMIT or list of str) Presentation status as a list of one or more strings, e.g. [ "okay" ]
- wcUrl (OMIT or str) CSS-WC server endpoint URL in the form "udp://<host>:<port>"
- tsUrl (OMIT or str) CSS-TS server endpoint WebSocket URL
- teUrl (OMIT or str) CSS-TE server endpoint WebSocket URL
- timelines (OMIT or list of TimelineOption) List of timeline options.
- private (OMIT or Signalling that a property is to be omitted from a message) –
   Private data.

The attributes of the object have the same name as the CII message properties:

- •protocolVersion
- •mrsUrl
- •contentId
- •contentIdStatus
- •presentationStatus
- •wcUrl
- •tsUrl
- •teUrl
- •timelines
- •private

Properties are accessed as attributes of this object using the same name as their JSON property name.

Converting to and from JSON representation is performed using the pack() method and unpack() class method. Properties set to equal OMIT will be omitted when the message is packed to a JSON representation.

#### protocolVersion = OMIT

(read/write OMIT or "1.1") The protocol version being used by the server.

# mrsUrl = OMIT

(read/write OMIT or str) The URL of an MRS server known to the server

#### contentId = OMIT

(read/write OMIT or str) Content identifier (URL)

#### contentIdStatus = OMIT

(read/write OMIT or "partial" or "final") Content identifier status

#### presentationStatus = OMIT

(read/write OMIT or list of str) Presentation status, e.g. [ "okay" ]

#### wcUrl = OMIT

(read/write OMIT or str) CSS-WC server endpoint URL in form "udp://<host>:<port>"

#### tsUrl = OMIT

(read/write OMIT or str) CSS-TS server endpoint WebSocket URL

#### teUrl = OMIT

(read/write OMIT or str) CSS-TE server endpoint WebSocket URL

#### timelines = OMIT

(read/write OMIT or list`(:class:`TimelineOption)) Timeline options

#### private = OMIT

(OMIT or list of dict ) Private data as a list of dict objects that can be converted to JSON by json.dumps(). Each dict must contain at least a key called "type" with a URI string as its value.

#### classmethod allProperties()

Returns a list of all property names, whether OMITted or not

#### combine (diff)

Copies this CII object, and updates that copy with any properties (that are not omitted) in the CII object supplied as the *diff* argument. The updated copy is then returned.

**Parameters** diff - (CII) A CII object whose properties (that are not omitted) will be used to update the copy before it is returned.

new = old.combine(diff) is equivalent to the following operations:

```
new = old.copy()
new.update(diff)
```

# copy()

**Returns** a copy of this CII object. The copy is a deep copy.

#### definedProperties()

Returns a list of the names of properties whose value is not OMIT

#### classmethod diff (old, new)

#### **Parameters**

- old (CII) A CII object
- new (CII) A CII object

**Returns** CII object representing changes from old to new CII objects.

If in the new CII object a property is OMITted, it property won't appear in the returned CII object that represents the changes.

If in the old CII object a property is OMITted, but it has a non-omitted value in the new object, then it is assumed to be a change.

# pack()

Returns string containing JSON representation of this message.

**Throws ValueError** if there are values for properties that are not permitted.

#### classmethod unpack (msg)

Convert JSON string representation of this message encoded as a CII object.

Throws ValueError if not possible.

# update (diff)

Updates this CII object with the values of any properties (that are not omitted) in the CII object provided as the *diff* argument.

Note that this changes this object.

**Parameters** diff - (CII) A CII object whose properties (that are not omitted) will be used to update this CII object.

# **Timeline Option**

Object representing a CSS-CII Timeline Option used in the "timelines" property of a CII message.

# Initialisation takes the following parameters:

#### **Parameters**

- timelineSelector (str) The timeline selector
- unitsPerTick (int) Denominator of tick rate (in ticks per second) for the corresponding timeline
- unitsPerSecond (int) Numerator of tick rate (in ticks per second) for the corresponding timeline
- accuracy (OMIT or float) Optional indication of timeline accuracy
- **private** (OMIT or Signalling that a property is to be omitted from a message) Optional private data.

It represents a timeline selector and the tick rate of the timeline if that selector is used to request a timeline from the CSS-TS server. It is carried in a list in the timelines property of a CII message.

The tick rate of the timeline is expressed by the *unitsPerTick* and *unitsPerSecond* values. The tick rate in ticks per second is equal to *unitsPerTick / unitsPerSecond*.

Accuracy and private data are optional, but the other fields are mandatory.

The attributes of the object have the same name as the relevant CII message properties:

- •timelineSelector
- •unitsPerTick
- •unitsPerSecond
- •accuracy
- •private

Converting to and from JSON representation is performed using the pack() method and unpack() class method. Properties set to equal OMIT will be omitted when the message is packed to a JSON representation.

#### timelineSelector = OMIT

(str) The timeline selector

# unitsPerTick = OMIT

(int) The units per tick of the timeline

#### unitsPerSecond = OMIT

(int) The units per second of the timeline

#### accuracy = OMIT

(OMIT or float) The accuracy of the timeline with respect to the content in seconds.

#### private = OMIT

(OMIT or list of dict) Private data as a list of dict objects that can be converted to JSON by json.dumps(). Each dict must contain at least a key called "type" with a URI string as its value.

#### classmethod decode (struct)

Internal method used by a CII message object when unpacking to JSON format.

#### classmethod encode (item)

Internal class method used by a CII message object when packing to JSON format.

#### pack()

**Returns** string containing JSON presentation of this message.

#### classmethod unpack (msg)

Convert JSON string representation of this message encoded as a *TimelineOption* object. **Throws ValueError** if not possible.

# **CSS-CII Clients**

Module: dvbcss.protocol.client.cii

- Using CIIClient
- Using CIIClientConnection
- Classes
  - CIIClient
  - CIIClientConnection

There are two classes provided for implementing CSS-CII clients:

- CIIClient connects to a CII server and provides a CII message object representing the complete state of the server and notifies you of changes of state.
- CIIClientConnection provides a lower level connection to a CII server and only provides the messages received from the server. It does not maintain a model of the server state and does not work out when a received message constitutes a change.

An *example* client is provided in this package that uses the CIIClient class.

## **Using CIIClient**

This is the simplest class to use. Create it, passing the URL of the server to connect to, then call <code>connect()</code> and <code>disconnect()</code> to connect and disconnect from the server.

CIIClient maintains a local copy of the state of CII data the CIIClient.cii property and the most recently received CII message in CIIClient.latestCII.

You can use the class either by subclassing and overriding the various stub methods or by creating an instance and replacing the stub methods with your own function handlers dynamically.

Pass the WebSocket URL of the CII server when creating the *CIIClient* then call the *connect()* and *disconnect()* methods to connect and disconnect from the server. The *onXXX()* methods can be overriden to find out when connection or disconnection takes place, if there is a protocol error (e.g. a message was received that could not be parsed as CII) or when properties of the CII data change.

The CII state is kept in the Cii property of the object. This is updated with properties in CII messages that are received. Properties not included in a CII message are left unchanged.

Properties of the CII state whose value is <code>dvbcss.protocol.OMIT</code> have not been defined by the CII server.

```
from dvbcss.protocol.client.cii import CIIClient
class MyCIIClient(CIIClient):
    def onConnected(self):
       print "Connected!"
    def onDisconnected(self, code, reason):
        print "Disconnected :-("
    def onChange(self, propertyNames):
        print "The following CII properties have changed:
        for name in propertyNames:
            value = getattr(conn.cii, name)
            print " "+name+" is now: "+str(value)
    # one example of a handler for changes to a particular property 'contentId' in,
\hookrightarrow CII
    def onContentIdChange(self, newValue):
        print "The contentId property has changed to now be: "+str(newValue)
client = MyCIIClient("ws://127.0.0.1/cii")
client.connect()
time.sleep(60)
print "The current contentId is "+client.cii.contentId
time.sleep(60)
                  # wait only 60 more seconds then disconnect
client.disconnect()
```

The client runs in a separate thread managed by the websocket client library, so the *onXXX* methods are called while the main thread sleeps.

## **Using CIIClientConnection**

This is a lower level class, that only implements parsing of the incoming CII messages from the server. It does not detect if a message actually constitutes a change of state or not.

You can use the class either by subclassing and overriding the various stub methods or by creating an instance and replacing the stub methods with your own function handlers dynamically.

Pass the WebSocket URL of the CII server when creating the CIIClientConnection object then call the connect() and disconnect() methods to connect and disconnect from the server. The onXXX() methods can be overridden to find out when connection or disconnection takes place, if there is a protocol error (e.g. a message was received that could not be parsed as CII) or when a new CII message is received.

```
from dvbcss.protocol.client.cii import CIIClientConnection

class MyCIIClientConnection(CIIClientConnection):

   def onConnected(self):
        print "Connected!"
```

```
def onDisconnected(self, code, reason):
    print "Disconnected :-("

def onCii(self, cii):
    print "Received a CII message: "+str(cii)

client = MyCIIClientConnection("ws://127.0.0.1/cii")
client.connect()

time.sleep(60)  # run only for 60 seconds then disconnect
client.disconnect()
```

#### **Classes**

#### **CIIClient**

```
class dvbcss.protocol.client.cii.CIIClient(ciiUrl)
```

Manages a CSS-CII protocol connection to a CSS-CII Server and notifies of changes to CII state.

Use by subclassing and overriding the following methods:

- •onConnected()
- •onDisconnected()
- •onChange()
- •individual onXXXXChange() methods named after each CII property
- •onCiiReceived() (do not use, by preference)

If you do not wish to subclass, you can instead create an instance of this class and replace the methods listed above with your own functions dynamically.

The <code>connect()</code> and <code>disconnect()</code> methods connect and disconnect the connection to the server and <code>getStatusSummary()</code> provides a human readable summary of CII state.

This object also provides properties you can query:

- •cii represents the current state of CII at the server
- latestCII is the most recently CII message received from the server
- $\bullet \textit{connected}$  indicates whether the connection is currently connect

## **Initialisation takes the following parameters:**

```
Parameters ciiUrl - (str) The WebSocket URL of the CSS-CII Server (e.g. "ws://127.0.0.1/myservice/cii")
```

#### connected

True if currently connected to the server, otherwise False.

#### cii

(CII) CII object representing the CII state at the server

#### latestCII

(CII or None) The most recent CII message received from the server or None if nothing has yet been received.

## connect()

Start the client by trying to open the connection.

Throws ConnectionError There was a problem that meant it was not possible to connect.

#### disconnect()

Disconnect from the server.

## onChange (changedPropertyNames)

This method is called when a CII message is received from the server that causes one or more of the CII properties to change to a different value.

**Parameters** changedPropertyNames – A list of str names of the properties that have changed. Query the *cii* attribute to find out the new values.

## onCiiReceived(newCii)

This method is called when a CII message is received, but before any 'onXXXXChange()' handlers (if any) are called. It is called even if the message does not result in a change to CII state held locally.

By preference is recommended to use the 'onXXXXChange()' handlers instead since these will only be called if there is an actual change to the value of a property in CII state.

This is a stub for this method. Sub-classes should implement it.

**Parameters** cii – A CII object representing the received message.

#### onConnected()

This method is called when the connection is opened.

This is a stub for this method. Sub-classes should implement it.

#### onContentIdChange (newValue)

Called when the contentId property of the CII message has been changed by a state update from the CII Server.

This is a stub for this method. Sub-classes should implement it.

**Parameters** newValue – The new value for this property.

#### onContentIdStatusChange (newValue)

Called when the contentIdStatus property of the CII message has been changed by a state update from the CII Server.

This is a stub for this method. Sub-classes should implement it.

**Parameters** newValue – The new value for this property.

#### onDisconnected(code, reason=None)

This method is called when the connection is closed.

This is a stub for this method. Sub-classes should implement it.

# **Parameters**

- code (int) The connection closure code to be sent in the WebSocket disconnect frame
- ullet reason (str or None) The human readable reason for the closure

#### onMrsUrlChange (newValue)

Called when the mrsUrl property of the CII message has been changed by a state update from the CII Server.

This is a stub for this method. Sub-classes should implement it.

**Parameters** newValue – The new value for this property.

#### onPresentationStatusChange (newValue)

Called when the presentationStatus property of the CII message has been changed by a state update from the CII Server.

This is a stub for this method. Sub-classes should implement it.

**Parameters** newValue – The new value for this property.

#### onPrivateChange (newValue)

Called when the private property of the CII message has been changed by a state update from the CII Server.

This is a stub for this method. Sub-classes should implement it.

**Parameters** newValue – The new value for this property.

#### onProtocolError (msg)

This method is called when there has been an error in the use of the CII protocol - e.g. receiving the wrong kind of message.

This is a stub for this method. Sub-classes should implement it.

**Parameters** msg – A str description of the problem.

# onProtocolVersionChange (newValue)

Called when the protocol Version property of the CII message has been changed by a state update from the CII Server.

This is a stub for this method. Sub-classes should implement it.

**Parameters** newValue – The new value for this property.

#### onTeUrlChange (newValue)

Called when the teUrl property of the CII message has been changed by a state update from the CII Server.

This is a stub for this method. Sub-classes should implement it.

Parameters newValue - The new value for this property.

#### onTimelinesChange(newValue)

Called when the timelines property of the CII message has been changed by a state update from the CII Server.

This is a stub for this method. Sub-classes should implement it.

**Parameters** newValue – The new value for this property.

# onTsUrlChange (newValue)

Called when the tsUrl property of the CII message has been changed by a state update from the CII Server.

This is a stub for this method. Sub-classes should implement it.

**Parameters** newValue – The new value for this property.

# onWcUrlChange (newValue)

Called when the wcUrl property of the CII message has been changed by a state update from the CII Server.

This is a stub for this method. Sub-classes should implement it.

**Parameters** newValue – The new value for this property.

#### **CIIClientConnection**

```
class dvbcss.protocol.client.cii.CIIClientConnection (url)
```

Simple object for connecting to a CSS-CII server and handling the connection.

Use by subclassing and overriding the following methods:

- •onConnected()
- •onDisconnected()
- •onCII()
- •onProtocolError()

If you do not wish to subclass, you can instead create an instance of this class and replace the methods listed above with your own functions dynamically.

#### **Initialisation takes the following parameters:**

```
Param url (str) The WebSocket URL of the CII Server to connect to. E.g. "ws://127.0.0.1/mysystem/cii"
```

#### connect()

Open the connection.

:throws ConnectionError if there was a problem and the connection could not be opened.

#### connected

True if the connection is connect, otherwise False

```
disconnect (code=1001, reason='')
```

Close the connection.

# **Parameters**

- code (optional int) The connection closure code to be sent in the WebSocket disconnect frame
- reason (optional str) The human readable reason for the closure

# onCII (cii)

This method is called when a CII message is received from the server.

This is a stub for this method. Sub-classes should implement it.

**Parameters** cii – A CII object representing the received message.

#### onConnected()

This method is called when the connection is opened.

This is a stub for this method. Sub-classes should implement it.

# onDisconnected(code, reason=None)

This method is called when the connection is closed.

This is a stub for this method. Sub-classes should implement it.

## **Parameters**

- code (int) The connection closure code to be sent in the WebSocket disconnect frame
- reason (str or None) The human readable reason for the closure

# "pydvbcss - a library implementing DVB protocols for Companion Screen Synchronisation, Release 0.4.1-release

#### onProtocolError (msg)

This method is called when there has been an error in the use of the CII protocol - e.g. receiving the wrong kind of message.

This is a stub for this method. Sub-classes should implement it.

**Parameters** msg – A str description of the problem.

# **CSS-CII Servers**

Module: dvbcss.protocol.server.cii

- Classes
  - CIIServer CII Server handler for cherrypy

#### **Classes**

# **CIIServer - CII Server handler for cherrypy**

This package provides objects for representing messages exchanged via the DVB CSS-CII protocol and for implementing clients and servers.

The CII protocol is a mechanism for sending state updates from server to client. The state of the server can be represented by a CII message where every property is populated with a value. The server can send complete CII messages or partial ones containing only the properties that have changed value since the last message. The client must track these changes to maintain its own local up-to-date copy of the complete state.

Modules for using the CSS-CII protocol:

- dvbcss.protocol.cii: objects for representing and packing/unpacking the CSS-CII protocol messages.
- dvbcss.protocol.client.cii: implementations of a client for a CSS-CII connection.
- dvbcss.protocol.server.cii: implementations of a server for a CSS-CII connection.

# **CSS-TS** protocol

## **CSS-TS Protocol introduction**

Here is a quick introduction to the CSS-TS protocol. For full details, refer to the DVB specification ETSI 103 286 part 2.

The CSS-TS protocol is for *Timeline Synchronisation*. Via this protocol, the server (e.g. TV) pushes timestamps to the client (e.g. companion) to keep it up-to-date on the progress of a particular timeline. The timeline to use is requested by the client at the beginning of the interaction.

A client can also report its own timing and what range of timings it can cope with. This allows the client to negotiate a mutually achievable timing with the server, although the server is under no obligation and can choose to ignore this information.

It is a WebSockets based protocol and messages are in JSON format.

- Sequence of interaction
- Determining timeline selection and availability
- What does a timestamp convey?

# Sequence of interaction

The client is assumed to already know the WebSocket URL for the CSS-TS server (usually from the information received via the *CSS-CII protocol*).

- 1. The client connects to the CSS-TS server. Either this is refused via an HTTP status code response, or it is accepted.
- 2. The client then immediately sends an initial SetupData message to request the timeline to synchronise with.
- 3. The server then starts sending back <code>ControlTimestamp</code> messages that update the client as to the state of that timeline. This state says either that the timeline is currently unavailable, or that it is available, and here is how to calculate the timeline position from the wall clock position. The server sends as frequently or infrequently as it likes, but will at least send them if there is a meaningful change in the timeline.
- 4. The client can, optionally, send its own AptEptLpt messages to inform the server of what it is doing, and the range of different timings it can achieve for its media (e.g. what is the earliest and latest timings it can achieve). However this is purely informative. A server is not obliged to do anything with this information.

# Determining timeline selection and availability

The SetupData message conveys to the CSS-TS server details of what timeline the client wants to synchronise to.

The CSS-TS server determines, at any given moment, if a timeline is available by checking if:

- 1. the stem matches the current content identifier for what is being presented at the server (meaning that the stem matches the left hand most subset of the content id);
- 2. and the timeline selector identifies a timeline that exists for the content being presented at the server.

While the above is true, the timeline is "available". While it is not true, it is "unavailable". The CSS-TS connection is kept open irrespective of timeline availability. The server indicates changes in availability via the <code>ControlTimestamp</code> messages it sends.

Example SetupData message; requesting a PTS timeline for a particular DVB broadcast channel, but not being specific about which event (programme in the EPG):

```
"contentIdStem" : "dvb://233a.1004.1044",
    "timelineSelector" : "urn:dvb:css:timeline:pts"
}
```

# What does a timestamp convey?

It represents a relationship between Wall Clock time and the timeline of the content being presented by the TV Device. It is sometimes referred to as a *(point of) correlation* between the wall clock and the timeline.

This relationship can be visualised as a line that maps from wall clock time (on one axis) to timeline time (on the other axis). The (content-time, wall-clock-time) correlation is a point on the line. The timelineSpeedMultiplier represents the slope. The tick rates of each timeline are the units (the scale of each axis).

The CSS-TS server sends *ControlTimestamp* messages to clients, and clients can, optionally, send back AptEptLpt messages.

A ControlTimestamp can also tell a client if a timeline is unavailable by having null values for the contentTime and timelineSpeedMultiplier properties. Non-null values mean the timeline is available.

AptEptLpt messages enables a client to inform a server of what time it is presenting at (the "actual" part of the timestamp) and also to indicate the earliest and latest times it could present. It is, in effect, three correlations bundled into one message, to represent each of these three aspects. Earliest and Latest correlations are allowed to have -infinity and +infinity for the wall clock time to indicate that the client has no limits on how early, or late, it can present.

An example ControlTimestamp indicating the timeline is unavailable:

```
"contentTime" : null,
    "wallClockTime" : "116012000000",
    "timelineSpeedMultiplier" : null
}
```

An example ControlTimestamp providing a correlation for an available timeline:

```
"contentTime" : "834188",
    "wallClockTime" : "116012000000",
    "timelineSpeedMultiplier" : 1.0
}
```

An example of an AptEptLpt message, indicating the current presentation timing being used by the client; a limit on how early it can present; but no limit on how long it can delay (buffer):

# **CSS-TS Message objects**

Module: dvbcss.protocol.ts

```
Examples
+/- infinity
Classes
- setup-data
```

- Control Timestamp
- AptEptLpt (Actual, Earliest and Latest Presentation Timestamp)
- Timestamp

A SetupData object represents a setup-data message sent by a client to a server immediately after opening a CSS-TS protocol connection.

A Control Timestamp object represents a Control Timestamp message sent by the server to the client.

A AptEptLpt object represents an Actual, Earliest and Latest Presentation Timestamp message that may be sent by a client to the server.

The *Timestamp* objects are used in the above message objects to represent the relationship between wall clock time and content (timeline) time.

# **Examples**

SetupData examples:

```
>>> from dvbcss.protocol.ts import SetupData
>>> from dvbcss.protocol import OMIT

>>> s = SetupData(timelineSelector="urn:dvb:css:timeline:pts", ciStem="dvb://1004")
>>> s.pack()
'{"timelineSelector": "urn:dvb:css:timeline:pts", "contentIdStem": "dvb://1004"}'
```

```
>>> jsonMessage = \"""\
... { "timelineSelector":"urn:dvb:css:timeline:temi:1:1",
... "contentIdStem":""
... }
... \"""
>>> SetupData.unpack(jsonMessage)
SetupData(ciStem="", timelineSelector="urn:dvb:css:timeline:temi:1:1", private=OMIT)
```

## ControlTimestamp examples:

```
>>> jsonMessage = \"""\
... { "contentTime" : "1003847",
... "wallClockTime" : "348957623498576",
... "timelineSpeedMultiplier" : 2.0
... }
... \"""
>>> c = ControlTimestamp.unpack(jsonMessage)
>>> c.timestamp.contentTime
1003847
>>> c.timestamp.wallClockTime
348957623498576
```

```
>>> c.timelineSpeedMultiplier
2.0
```

Actual, Earliest and Latest Presentation Timestamp examples:

```
>>> jsonMessage = \"""\
... { "earliest" : { "contentTime" : "1000", "wallClockTime": "10059237" },
... "latest" : { "contentTime" : "1000", "wallClockTime": "19284782" },
... "actual" : { "contentTime" : "1005", "wallClockTime": "10947820" }
... }
... \"""
>>> ael=AptEptLpt.unpack(jsonMessage)
>>> ael.actual.contentTime
1005
>>> ael.actual.wallClockTime
10947820
```

# +/- infinity

For certain timestamp messages it is permissible to convey a time value that is either plus or minus infinity. Use the python float to express these values as follows:

```
>>> float("+inf")
inf

>>> float("-inf")
-inf
```

# **Classes**

# setup-data

class dvbcss.protocol.ts.SetupData (contentIdStem, timelineSelector, private=OMIT)
 Object representing a CSS-TS Setup-Data message.

This carries a content identifier stem and a timeline selector string, and is used, in effect, to request the timeline to be synchronised to via the CSS-TS protocol.

## **Initialisation takes the following parameters:**

# **Parameters**

- **contentIdStem** (*str*) The content identifier stem.
- timelineSelector (str) The timeline selector

private (OMIT or Signalling that a property is to be omitted from a message) –
 Optional private data.

The attributes of the object have the same name as the SetupData message properties:

- •contentIdStem
- •timelineSelector
- •private

Converting to and from JSON representation is performed using the pack() method and unpack() class method. Properties set to equal OMIT will be omitted when the message is packed to a JSON representation.

#### contentIdStem

(read/write str) The stem (subset starting from the LHS) of a content identifier

#### timelineSelector

(read/write str) The timeline selector

#### private = OMIT

(read/write OMIT or Signalling that a property is to be omitted from a message) Optional private data.

# copy()

**Returns** a copy of this SetupData object. Note that this does NOT deep copy any private data.

#### pack()

**Returns** string containing JSON representation of this message.

Throws ValueError if there are values for properties that are not permitted.

#### classmethod unpack (msg)

Convert JSON string representation of this message encoded as a SetupData object. **Throws ValueError** if not possible.

## **Control Timestamp**

class dvbcss.protocol.ts.ControlTimestamp (timestamp, timelineSpeedMultiplier)
 Object representing a CSS-TS Control Timestamp message.

#### **Initialisation takes the following parameters:**

#### **Parameters**

- timestamp (Timestamp) carries the *contentTime* and *wallClockTime* properties of the Control Timestamp
- timelineSpeedMultiplier (float or None) the timeline speed multiplier

The attributes of the object have the following relationship to the message properties:

- •timestamp
- •timelineSpeedMultiplier

Converting to and from JSON representation is performed using the pack() method and unpack() class method.

#### timestamp

(read/write Timestamp) Timestamp object representing the contentTime and wallClock-Time parts of the timestamp)

#### timelineSpeedMultiplier

(read/write float or None) Timeline speed. For example: 1 = normal, 0 = pause, -0.5 = half speed reverse. Use *None* only when the Control Timestamp is supposed to indicate that the timeline is unavailable.

# copy()

**Returns** a deep copy of this Control Timestamp object

#### pack()

**Returns** string containing JSON representation of this message.

**Throws ValueError** if there are values for properties that are not permitted.

## classmethod unpack (msg)

Convert JSON string representation of this message encoded as a ControlTimestamp object.

Throws ValueError if not possible.

# AptEptLpt (Actual, Earliest and Latest Presentation Timestamp)

Object representing a CSS-TS Actual, Earliest and Latest Presentation Timestamp message.

# Initialisation takes the following parameters:

#### **Parameters**

- actual (OMIT or Timestamp) Optional timestamp representing the actual presentation timing
- **earliest** (OMIT or Timestamp) Timestamp representing the earliest possible presentation timing
- latest (OMIT or Timestamp) Timestamp representing the latest possible presentation timing

For the *actual presentation timestamp*, the contentTime and wallClockTime must both be non-null integer values.

For the *earliest presentation timestamp*, the contentTime must be a non-null integer. wallClockTime can be a non-null integer or *plus infinity* 

For the *latest presentation timestamp*, the contentTime must be a non-null integer. wallClockTime can be a non-null integer or *minus infinity* 

The attributes of the object have the same names as the Actual, Earliest and Latest presentation timestamp message properties:

- •actual
- •earliest
- •latest

Converting to and from JSON representation is performed using the pack() method and unpack() class method. If values of properties do not meet the requirements described above, then pack() will raise ValueError exceptions.

#### actual

(read/write OMIT or Timestamp) Actual presentation timestamp

#### earliest

(read/write <code>Timestamp</code>) Earliest presentation timestamp. The wallClockTime property must be an int or float ("+inf"). It must not be float ("-inf").

#### latest

(read/write <code>Timestamp</code>) Latest presentation timestamp. The wallClockTime property must be an int or float ("-inf"). It must not be float ("+inf").

#### copy()

**Returns** a deep copy of this AptEptLpt object

#### pack()

**Returns** string containing JSON representation of this message.

**Throws ValueError** if there are values for properties that are not permitted.

#### classmethod unpack (msg)

Convert JSON string representation of this message encoded as a AptEptLpt object.

Throws ValueError if not possible.

# **Timestamp**

This object does not directly represent a message, but is instead used by ControlTimestamp and AptEptLpt as a representation of a correlation between a content time and a wall clock time.

```
class dvbcss.protocol.ts.Timestamp (contentTime, wallClockTime)
```

Object representing a Timestamp part(s) of a ControlTimestamp or AptEptLpt object.

# **Initialisation takes the following parameters:**

#### **Parameters**

- contentTime (None or int) The content time (time on timeline) part of a timestamp
- wallClockTime (int or +/- infinity float ("+inf") or float ("-inf")) The wall clock time part of a timestamp

The values for contentTime and wallClockTime are allowed to be arbitrarily large precision integers because they are carried as a string in the JSON representation.

The attributes of the object have the same name as the corresponding message properties:

- •contentTime
- •wallClockTime

Converting to and from JSON representation is performed using the pack() method and unpack() class method.

#### contentTime

(read/write None or large int) The content time part of a timestamp

#### wallClockTime

(read/write large int or float("+inf") or float("-inf") ) The wall clock time part
of a timestamp

# **CSS-TS Clients**

Module: dvbcss.protocol.client.ts

- Using TSClientClockController
- Using TSClientConnection
- Classes
  - TSClientConnection
  - TSClientClockController

There are two classes provided for implementing CSS-TS clients:

- TSClientClockController wraps a TSClientConnection and provides a higher level interface that provides information about timeline availability and drives a clock object to match the timeline.
- *TSClientConnection* implements the core functionality of connecting to a CSS-TS server and providing methods and callbacks to manage the connection and send and receive *timestamp* messages.

An example client is provided in this package that uses the TSClientClockController class.

# Using TSClientClockController

This class provides a high level interface that drives a *CorrelatedClock* object to match the timeline provided by a CSS-TS server. Subclass to get notifications of connection, disconnection and timing changes or changes in timeline availability.

Create it, passing the URL of the server to connect to, and a connect and <code>disconnect()</code> to connect and disconnect from the server.

The clock you provide must be a <code>CorrelatedClock</code> object and the parent clock of that clock must represent the <code>wall clock</code>. The tick rate of this clock must match that of the timeline and the tick rate of the wall clock must be 1 tick per nanosecond (1e9 ticks per second). This should therefore be used in conjunction with a <code>WallClockClient</code> to ensure the wall clock is meaningfully synchronised to the same server.

The TSClientClockController object maintains the connection and automatically adjusts the correlation of the clock to synchronise it, using the information in the Control Timestamps received from the server. It adjusts the speed() to match speed changes of the timeline. It also sets the availability of the clock to reflect the availability of the timeline.

You can set a minimum threshold for how much the timing must change before the the timeline clock will be adjusted.

You can also provide separate clock objects to represent the earliest and latest presentation timings that your application can achieve (and that you wish to convey to the server). These must also be <code>CorrelatedClock</code> objects. Use the <code>TSClientClockController.sendAptEptLpt()</code> method to cause that information to be sent to the server.

A simple example:

```
# NOTE: need a Wall Clock Client too (not shown in this example)
       to ensure wallClock is synchronised
class MyTSClient(TSClientClockController):
   def onConnected(self):
       print "Conected!"
   def onDisconnected(self):
       print "Disconnected :-("
   def onTimelineAvailable(self):
       print "Timeline is available!"
   def onTimelineUnavailable(self):
       print "Timeline is not available :-("
   def onTimingChange(self, speedHasChanged):
       print "Timing of clock has been adjusted."
        if speedHasChanged:
           print "The speed of the clock has altered."
# make connection. Want PTS timeline for any DVB service.
client = MyTSClient("ws://192.168.1.1:7682/ts",
                    "dvb://",
                    "urn:dvb:css:timeline:pts",
                   timelineClock)
client.connect()
for i in range (0,60):
   time.sleep(1)
   print "Timeline available?", timelineClock.isAvailable()
   if timelineClock.isAvailable():
       print "Timeline currently at tick value = ", timelineClock.ticks
                   ... and moving at speed = ", timelineClock.speed
       print "
client.disconnect()
```

The client runs in a separate thread managed by the websocket client library, so the *onXXX* methods are called while the main thread sleeps.

#### Using TSClientConnection

This class provides the lowest level interface to a CSS-TS server. It only implements the parsing of incoming Control Timestamp messages and sending of outgoing Actual, Earliest and Latest Presentation Timestamp messages. It does not try to understand the meaning of the messages sent or received.

You can use the class either by subclassing and overriding the various stub methods or by creating an instance and replacing the stub methods with your own function handlers dynamically.

Pass the WebSocket URL of the CSS-TS server during initialisation then call the <code>connect()</code> and <code>disconnect()</code> methods to connect and disconnect from the server. The <code>onXXX()</code> methods are called when connection or disconnection takes place, if there is a protocol error (e.g. a message was received that could not be parsed as Control Timestamp) or a new Control Timestamp is received.

A simple example:

```
from dvbcss.protocol.client.ts import TSClientConnection
from dvbcss.protocol.ts import AptEptLpt
from dvbcss.protocol import OMIT
class MyClientConnection(TSClientConnection):
   def onConnected(self):
       print "Connected!"
       e = Timestamp(0, float("-inf"))
       1 = Timestamp(0, float("+inf"))
        aptEptLpt = AptEptLpt(earliest=e, latest=l, actual=OMIT)
        client.sendTimestamp(aptEptLpt)
   def onDisconnected(self, code, reason):
       print "Disconnected :-("
   def onControlTimestamp(self, ct):
       print "Received a ControlTimestamp: "+str(ct)
# make connection. Want PTS timeline for any DVB service.
client = MyTSClientConnection("ws://127.0.0.1/ts", "dvb://", "urn:dvb:css:timeline:pts
client.connect()
time.sleep(60)
                  # run only for 60 seconds then disconnect
client.disconnect()
```

#### **Classes**

#### **TSClientConnection**

Use by subclassing and overriding the following methods or assigning your own functions to them at runtime:

```
    onConnected()
    onDisconnected()
    onControlTimestamp()
    onProtocolError()
```

If you do not wish to subclass, you can instead create an instance of this class and replace the methods listed above with your own functions dynamically.

Use the sendTimestamp () method to send Actual, Earliest and Latest Presentation Timestamps to the server.

This class has the following properties:

•connected (read only) whether the client is connected or not

## **Initialisation takes the following parameters:**

#### **Parameters**

• **url** (*str*) – The WebSocket URL of the TS Server to connect to. E.g. "ws://127.0.0.1/mysystem/ts"

- **contentIdStem** (*str*) The stem of the content id to be included in the SetupData message that is sent as soon as the connection is opened.
- **timelineSelector** (*str*) The timeline selector to be included in the SetupData message that is sent as soon as the connection is opened.

#### connect()

Open the connection.

**Throws ConnectionError** if there was a problem and the connection could not be opened.

#### connected

This property is True if the connection is connect, otherwise False

### disconnect (code=1001, reason='')

Close the connection.

#### **Parameters**

- code (optional int) The connection closure code to be sent in the WebSocket disconnect frame
- reason (optional str) The human readable reason for the closure

#### onConnected()

This method is called when the connection is opened and the setup-data message has been sent.

This is a stub for this method. Sub-classes should implement it.

### onControlTimestamp (controlTimestamp)

This method is called when a Control Timestamp message is received from the server.

This is a stub for this method. Sub-classes should implement it.

**Parameters controlTimestamp** - A ControlTimestamp object representing the received message.

#### onDisconnected()

This method is called when the connection is closed.

This is a stub for this method. Sub-classes should implement it.

# $\verb"onProtocolError" (\mathit{msg}\,)$

This method is called when there has been an error in the use of the TS protocol - e.g. receiving the wrong kind of message.

This is a stub for this method. Sub-classes should implement it.

**Parameters** msg – A str description of the problem.

# sendTimestamp (aptEptLpt)

Send an Actual, Earliest and Latest Presentation Timestamp message to the TS Server.

**Parameters** aptEptLpt – The AptEptLpt object representing the Actual, Earliest and Latest Presentation Timestamp to be sent.

#### **TSClientClockController**

This class manages a CSS-TS protocol connection and controls a *CorrelatedClock* to synchronise it to the timeline provided by the server.

Subclass and override the following methods when using this class:

- •onConnected()
- •onDisconnected()
- •onTimingChange()
- •onTimelineAvailable()
- •onTimelineUnavailable()
- •onProtocolError()

If you do not wish to subclass, you can instead create an instance of this class and replace the methods listed above with your own functions dynamically.

Create an instance of this class and use the <code>connect()</code> and <code>disconnect()</code> methods to start and stop its connection to the server. The <code>contentIdStem</code> and <code>timelineSelector</code> you specify are sent to the server in a <code>SetupData</code> message to choose the timeline to receive from the server.

While connected, while the timeline is available, the timelineClock you provided will have its *correlation* updated to keep it in sync with the timeline received from the server.

The *speed* property of the timeline clock will also be adjusted to match the timeline speed indicated by the server. For example: it will be set to zero when the timeline is paused, or 2.0 when the timeline speed is x2. The *tickRate* property of the clock is not changed.

Requirements for the timeline clock you provide:

- •The tickRate of the **timeline clock** must match that of the timeline.
- •Its parent must represent the wall clock
- •The wall clock must have a ~dvbcss.clock.CorrelatedClock.tickRate that matches the wall clock tick rate.

The TSClientClockController has the following properties:

- •connected (read only) is the client connected?
- •timelineAvailable (read only) is the timeline available?
- $\bullet \textit{latestCt} \textbf{ (read only) is the most recently received } \textit{ControlTimestamp message}$
- •earliestClock (read/write) A clock object representing earliest possible presentation timing, or None
- •latestClock (read/write) A clock object representing latest possible presentation timing, or None

# Initialisation takes the following parameters:

#### **Parameters**

• **url** (*str*) – The WebSocket URL of the TS Server to connect to. E.g. "ws://127.0.0.1/mysystem/ts"

- **contentIdStem** (*str*) The stem of the content id to be included in the SetupData message that is sent as soon as the connection is opened.
- **timelineSelector** (*str*) The timeline selector to be included in the SetupData message that is sent as soon as the connection is opened.
- timelineClock (CorrelatedClock) A clock object whose parent must represent the wall clock.
- **correlationChangeThresholdSecs** (*float*) Minimum threshold for the change in the timeline (in units of seconds) that will result in the timeline clock being adjusted.
- earliestClock (CorrelatedClock or None) An optional clock object representing the earliest possible presentation timing that this client can achieve (expressed on the same timeline)
- latestClock (CorrelatedClock or None) An optional clock object representing the latest possible presentation timing that this client can achieve (expressed on the same timeline)

#### connected

(bool) True if currently connected to the server, otherwise False.

#### latestCt

(Control Timestamp) A copy of the most recently received Control Timestamp.

#### earliestClock

None or a *CorrelatedClock* correlated to the WallClock representing the earliest possible presentation timing.

### latestClock

None or a *CorrelatedClock* correlated to the WallClock representing the latest possible presentation timing.

#### connect()

Start the client by trying to open the connection.

If the connection opens successfully, a SetupData message will be sent automatically.

**Throws ConnectionError** if there was a problem and the connection could not be opened.

#### disconnect()

Disconnect from the server.

## getStatusSummary()

**Returns str** A human readable string describing the state of the timeline and the connection.

# ${\tt onConnected}\,(\,)$

This method is called when the connection is opened and the setup-data message has been sent.

This is a stub for this method. Sub-classes should implement it.

#### onDisconnected()

This method is called when the connection is closed.

This is a stub for this method. Sub-classes should implement it.

# onProtocolError (msg)

This method is called when there has been an error in the use of the CII protocol - e.g. receiving the wrong kind of message.

This is a stub for this method. Sub-classes should implement it.

**Parameters** msg – A str description of the problem.

#### onTimelineAvailable()

This method is called when the server indicates that the timeline is available.

This is a stub for this method. Sub-classes should implement it.

# onTimelineUnavailable()

This method is called when the server indicates that the timeline is unavailable.

This is a stub for this method. Sub-classes should implement it.

# onTimingChange (speedChanged)

This method is called when the server indicates that the timeline timing has changed.

This means that a received Control Timestamp has changed the timing of the clock relative to the wall clock by the threshold amount or more, or that the speed of the timeline has changed. (as indicated by the timelineSpeedMultiplier property of received Control Timestamps).

This is a stub for this method. Sub-classes should implement it.

**Parameters** speedChanged – (bool) True if the speed of the timeline has changed, otherwise False.

#### sendAptEptLpt (includeApt=True)

Sends an Actual, Earliest and Latest presentation timestamp to the CSS-TS server.

- •The EPT is derived from the <code>earliestClock</code> property, if it is not None and it is a clock that is available.
- •The LPT is derived from the <code>latestClock</code> property, if it is not None and it is a clock that is available.
- •The APT is only included if the includeApt argument is True (default=True) and it is a clock that is available.

**Parameters includeApt** – (bool) Set to False if the Actual Presentation Timestamp is *not* to be included in the message (default=True)

# timelineAvailable

(bool) True if the most recently received Control Timestamp indicates that the timeline is available.

Changed in version 0.4: It is now recommended to not use this method. Instead, use the <code>isAvailable()</code> method of a <code>clock</code> instead.

# **CSS-TS Servers**

Module: dvbcss.protocol.server.ts

- Classes
  - TSServer
  - TimelineSource
  - SimpleTimelineSource
  - SimpleClockTimelineSource
- Functions
  - ciMatchesStem

- isControlTimestampChanged

**Classes** 

**TSServer** 

**TimelineSource** 

**SimpleTimelineSource** 

SimpleClockTimelineSource

**Functions** 

ciMatchesStem

# isControlTimestampChanged

This package provides objects for representing messages exchanged via the DVB CSS-TS protocol and for implementing clients and servers.

The TS protocol is a mechanism for a server to share timeline position and playback speed with a client. In effect it enables a client to synchronise its understanding of the progress of media presentation with that of a server, in terms of a particular timeline.

The client initially sends a <code>SetupData</code> message to specify what timeline it wants to synchronise in terms of. The server then periodically sends <code>ControlTimestamp</code> messages to inform the client of the state of presentation timing. The client can also send <code>AptEptLpt</code> (Actual, Earliest and Latest Presentation Timestamp) messages to the server to inform it of its playback timing and range of playback timings it can achieve.

The client implementation in this library can control a <code>CorrelatedClock</code>, synchronising it to the timeline. The server implementation in this library uses <code>CorrelatedClock</code> objects as its source of timelines that it is to share with clients.

Modules for using the CSS-TS protocol:

- dvbcss.protocol.ts: objects for representing and packing/unpacking the CSS-TS protocol messages.
- dvbcss.protocol.client.ts: implementation of a client for a CSS-TS connection.
- dvbcss.protocol.server.ts: implementation of a server for a CSS-TS connection.

# **CSS-WC** protocol

# **CSS-WC Protocol Introduction**

Here is a quick introduction to the CSS-WC protocol. For full details, refer to the DVB specification ETSI 103 286 part 2.

The CSS-WC protocol is for establishing *Wall clock synchronisation* - meaning that there is a common synchronised sense of time (a "wall clock") between the server (e.g. TV) and client (e.g. companion). This common wall clock is used in the CSS-TS protocol to make it immune to network delays.

The client uses the information carried in the protocol to estimate the server wall clock and attempt to compensate for network latency. This is a connectionless UDP protocol similar to NTP's client-server mode of operation, but much simplified and not intended to set the system real-time clock.

- Sequence of interaction
- Synchronising the wall clock
- Message format

# Sequence of interaction


The client is assumed to already know the host and port number of the CSS-WC server (usually from the information received via the *CSS-CII protocol*).

- 1. The client sends a Wall Clock protocol "request" message to the server.
- 2. The server sends back a Wall Clock protocol "response" message to the client.
- 3. If the server is able to more accurately measure when it sent a message *after* it has done so, then it can optionally send a "follow-up response" with this information.

The client repeats this process as often as it needs to.

# Synchronising the wall clock

The client notes the time at which the request is sent and the response received, and by the server including the times at which it received the request and sent its response. Using this information the client can estimate the relationship between the time of its clock and that of the server. It can also calculate an error bound on this (known as dispersion):



## Relationship expressed as an estimated offset:

• Offset between local clock and server wall clock is ((t3 + t2) - (t4 + t1))/2

## Relationship expressed as a correlation:

- When local clock is (t1 + t4)/2
- ... the server wall clock is estimated to be (t2 + t3)/2

The DVB specification (part 2) contains an annex that goes into more detail on the theory of how to calculate dispersion and how a client can use this as part of a simple algorithm to align its wall clock.

# Message format

Requests and responses both have the same fixed 32 byte binary message format. A WCMessage carries the following fields:

- Protocol version identifier
- Message **type** (request / response / response-before-follow-up / follow-up)
- The **precision** of the server's wall clock
- The maximum frequency error of the server's wall clock
- Timevalues (in NTP 64-bit time format, comprising a 32bit word carrying the number of nanoseconds and another 32bit word containing the number of seconds)
  - Originate timevalue: when the client sent the request.
  - Receive timevalue: when the server received the request.
  - Transmit timevalue: when the server sent the response.

The *precision*, *max freq error*, *receive timevalue* and *transmit timevalue* fields only have meaning in a response from a server. Their values do not matter in requests.

# **CSS-WC Message objects**

Module: dvbcss.protocol.wc

- Example usage
- Classes
  - WCMessage
  - Candidate

The WCMessage class represents a CSS-WC protocol message.

The Candidate class represents the measurement resulting from a request-response exchange of messages with a server. This is a "candidate" that could be used to update the client's estimate of the Wall Clock and is therefore used by a Wall Clock Client algorithm. A candidate is calculated from a <code>WCMessage</code> that represents a Wall Clock protocol response message received from a server.

A candidate can calculate the correlation needed to set a CorrelatedClock to model the server's Wall Clock.

# **Example usage**

Creating a request message at a Wall Clock Client:

# "pydvbcss - a library implementing DVB protocols for Companion Screen Synchronisation, Release 0.4.1-release

Processing a received response message at a Wall Clock Client:

```
>>> from dvbcss.protocol.wc import Candidate

>>> t4 = <nanoseconds-at-which-message-was-received>
>>> msg = WCMessage.unpack(receivedData)
>>> msg.msgtype
1
>>> c = Candidate(msg, t4)
>>> c.rtt
459734573
```

Creating a correlation to configure a :class: "dvbcss.clock.CorrelatedClock" representing the client estimate of the server's wall clock:

#### **Classes**

# **WCMessage**

```
class dvbcss.protocol.wc.WCMessage (msgtype, precision, maxFreqError, originate-
Nanos, receiveNanos, transmitNanos, originalO-
riginate=None)
```

Create object representing a CSS-WC wall clock request or response message.

#### **Initialisation takes the following parameters:**

## **Parameters**

- msgtype (int) Type of message. One of: TYPE\_REQUEST, TYPE\_RESPONSE, TYPE\_RESPONSE\_WITH\_FOLLOWUP and TYPE\_FOLLOWUP
- **precision** (*int*) Precision (of the server's wall clock) encoded in log base 2 seconds between -128 and +127 inclusive.
- maxFreqError (int) Maximum frequency error (of the server's wall clock) in units of 1/256ths ppm.
- $\bullet \ \, \textbf{originateNanos} \, (\textit{int}) O \\ \\ \text{riginate time value in integer number of nanoseconds} \\$
- receiveNanos (int) Receive timevalue in integer number of nanoseconds
- transmitNanos (int) Transmit timevalue in integer number of nanoseconds
- originalOriginate (None or (int, int)) Optional original encoding of the originate timevalue as (seconds, nanos). Overrides *originateNanos* if not *None*.

The originalOriginate parameter, if not None, overrides the originateNanos parameter.

Convert to and from a string containing the binary encoding of this message using the pack () method and unpack () class method.

#### msgtype

(read/write int) Type of message. 0=request, 1=response, 2=response-with-followup, 3=followup

#### precision

(read/write int) Precision encoded in log base 2 seconds between -128 and +127 inclusive. For example: -10 encodes a precision value of roughly 0.001 seconds.

#### maxFreqError

(read/write int) Maximum frequency error in units of 1/256ths ppm. For example: 12800 encodes a max freq error of 50ppm.

#### originateNanos

(read/write int) Originate timevalue in integer number of nanoseconds

#### receiveNanos

(read/write int) Receive timevalue in integer number of nanosecond

#### transmitNanos

(read/write int) Transmit timevalue in integer number of nanosecond

#### originalOriginate

(read/write None or (int, int)) Optional original encoding of the originate timevalue as (seconds, nanos). Overrides *originateNanos* when the message is packed if the value is not *None*.

#### $TYPE_FOLLOWUP = 3$

Constant: Message type 3 "follow-up response"

#### TYPE REQUEST = 0

Constant: Message type 0 "request"

#### TYPE RESPONSE = 1

Constant: Message type 1 "response with no follow-up"

#### TYPE\_RESPONSE\_WITH\_FOLLOWUP = 2

Constant: Message type 2 "response to be followed by a follow-up response"

## copy()

Duplicate this wallclock message object

#### classmethod encodePrecision (precisionSecs)

Convert a precision value in seconds to the format used in these messages

#### getMaxFreqError()

Get frequency error in ppm

# getPrecision()

Get precision value in fractions of a second

#### pack()

Pack wall clock message into binary representation.

**Returns** String containing the wall clock message in final bitstream form.

# setMaxFreqError(maxFreqErrorPpm)

Set freq error given a freq error represented as ppm

# setPrecision (precisionSecs)

Set precision value given a precision represented as factions of a second

#### classmethod unpack (data)

Class method that takes a string containing a wall clock message and unpacks it to a *WCMessage* object.

**Parameters data** (str) – String containing binary representation of a Wall Clock message as received from a client or server.

**Returns** *WCMessage* object representing the wall clock message.

#### **Candidate**

**class** dvbcss.protocol.wc.**Candidate** (*msg*, *nanosRx*)

This object represents a measurement "candidate" to be fed into a Wall Clock Client's algorithm. It is calculated from a *WCMessage* received as a response from a Wall Clock server.

This object requires that response comes from a Wall Clock Client that measured the *parent* of the clock that will be used to model the wall clock locally.


#### **Initialisation takes the following parameters:**

#### **Parameters**

- msg (WCMessage) Response message received from server
- nanosRx (int) the time, in nanoseconds, at which it was received (from the server)

Pass in a received WallClockMessage that is a response and this will represent the candidate data derived from that request-response interaction.

Populates properties of this objects with the candidate information. t1, t2, t3 and t4 represent the times of message sending and receiving as shown below:



It also calculates and provides, as properties, the round-trip time (rtt) and clock offset estimate (offset) based on this measurement.

All data is in units of nanoseconds, except for precision which is measured in seconds, and maximum frequency error which is measured in ppm.

A helper function <code>calcCorrelationFor()</code> makes it easy to calculate the <code>Correlation</code> needed to take this measurment candidate and use it to control a <code>CorrelatedClock</code>.

#### t1 = msg.originateNanos

(read only) The time "t1" at which the request was sent in the request-response measurement (nanoseconds)

#### t2 = msg.receiveNanos

(read only) The time "t2" at which the request was received in the request-response measurement (nanoseconds)

#### t3 = msg.transmitNanos

(read only) The time "t3" at which the response was sent in the request-response measurement (nanoseconds)

#### t4 = nanosRx

(read only) The time "t4" at which the response was received in the request-response measurement (nanoseconds)

#### offset = ((t3+t2)-(t4+t1))/2

(read only) Server<->client clock offset (nanoseconds)

#### rtt = (t4-t1)-(t3-t2)

(read only) Round trip time (nanoseconds)

#### isNanos = True

#### precision = msg.getPrecision()

(read only) The precision reported by the server in its response (units of factions of a second)

# maxFreqError = msg.getMaxFreqError()

(read only) The maximum frequency error reported by the server in its response (units of ppm)

#### msg = WCMessage

(read only WCMessage) The response message from which this candidate was derived

# calcCorrelationFor (clock, localMaxFreqErrorPpm=None)

Calculates and returns the Correlation for a CorrelatedClock that is equivalent to this candidate.

The returned correlation can then be applied to the clock to model the time at the server. This includes the error bounds information needed to enable the clock to correctly calculate dispersion.

#### **Parameters**

- **clock** *CorrelatedClock* that will model the server clock. Its parent must be the one that was measured for *t1* and *t4* this candidate.
- localMaxFreqErrorPpm Optional. By defeault the getRootMaxFreqError() of the clock is used. Provide this value to override that.

**Returns** Correlation representing this candidate, and that can be used with the CorrelatedClock.

**Note:** The parameters of the correlation are calculated by this function as follows:

```
•parentTicks = (t1' + t4') / 2
```

•initialError = precision + (rtt/2 + mfeC \* (t4 - t1) + mfeS \* (t3 - t2)) /  $10^9$ 

•errorGrowthRate = mfeC + mfeS

#### Where:

- •t1, t2, t3 and t4 are in units of nanoseconds
- •t1' and t4' are the same as t1 and t4 but converted to ticks of the parent of the specified clock
- •t2' and t3' are the same as t2 and t3 but converted to ticks of the specified clock
- •mfeC is the clock's getRootMaxFreqError(), converted from ppm to a fraction by dividing by  $10^6$
- •mfeS is the max freq error reported by the server, converted from ppm to a fraction by dividing by  $10^6$

New in version 0.4.

<sup>•</sup>**childTicks** = (t2' + t3') / 2

#### toTicks(clock)

Returns a new Candidate object the same as this one but whose measurements have been converted to match the timescale of a clock.

Raises NotImplementedError - This function has been deprecated.

**Warning:** Deprecated since version 0.4: This function has been deprecated because of the architectural change to taking taking readings from a different clock to the one that is adjusted.

Use <code>calcCorrelationFor()</code> instead as this will perform the necessary conversion to clock tick rate units as well as creating the correlation needed to configure that clock.

# **CSS-WC Clients**

Modules: dvbcss.protocol.client.wc | dvbcss.protocol.client.wc.algorithm

- Using a Wall Clock Client
- Algorithms
  - Dispersion algorithm
  - Simple algorithm
  - Writing new algorithms
  - Composable Filter and prediction algorithm
    - \* Round-trip time threshold Filter
    - \* Lowest dispersion candidate filter
    - \* Simple Predictor
    - \* Writing your own Filter
    - \* Writing your own Predictor
- Classes
  - WallClockClient
  - Dispersion algorithm
  - Most recent measurement algorithm
  - Filter and Prediction composable algorithms
    - \* Filters
    - \* Predictors
- Functions
  - Filter and Prediction algorithm creator
  - Candidate quality calculator

The WallClockClient class provides a complete Wall Clock Client implementation. It is used in conjunction with an algorithm for adjusting a clock object so that it mirrors the server's Wall Clock.

#### **Using a Wall Clock Client**

Recommended simplest use is to instantiate a WallClockClient and provide it with an instance of the LowestDispersionCandidate algorithm to control how it updates a clock.

A simple example that connects to a wall clock server at 192.168.0.115 port 6677 and sends requests once per second:

```
from dvbcss.clock import SysClock as SysClock
from dvbcss.protocol.client.wc import WallClockClient
from dvbcss.protocol.client.wc.algorithm import LowestDispersionCandidate

sysClock=SysClock()
wallClock=CorrelatedClock(sysClock,tickRate=1000000000)

algorithm = LowestDispersionCandidate(wallClock,repeatSecs=1,timeoutSecs=0.5)


bind = ("0.0.0.0", 6677)
server = ("192.168.0.115", 6677)

wc_client=WallClockClient(bind, server, wallClock, algorithm)
wc_client.start()

# wall clock client is now running in the background
```

After the start () method is called, the WallClockClient runs in a separate thread and execution continues.

WallClockClient is used by providing it with an object implementing the clock synchronisation algorithm. The Wall Clock client handles the protocol interaction (sending the requests and parsing the responses) at the times specified by the algorithm and passes the results of each request-response measurement (a Candidate) to the algorithm. The algorithm then adjusts the clock.



Changed in version 0.4: The measurement process involves taking a reading from the local clock when the request is about to be sent, and when the response is received. This measurement is taken from the *parent* of the clock you provide. The candidate represents a possible relationship between that (parent) clock and the Wall Clock of the server given the results of the request-response measurement. The algorithm processes this and makes a decision as to the *Correlation* that is to be used.

Although the WallClockClient class does not require the tickrate of the Wall Clock to be 1 tick per nanosecond, it is recommended to set it as such. This is because the next step (using the CSS-TS protocol) assumes a Wall Clock

ticking at this rate.

# **Algorithms**

The algorithm object determines when (and how often) a WallClockClient sends CSS-WC protocol requests and processes the results of requests and responses to adjust the clock object representing the Wall Clock.

### **Dispersion algorithm**

The LowestDispersionCandidate algorithm is the recommended algorithm. It uses the candidate with the lowest dispersion.

# Simple algorithm

The MostRecent algorithm is a simple naive algorithm that uses the most recent candidate irrespective of its quality (e.g. how long the round-trip time of the measurement was)

# Writing new algorithms

An algorithm is an object that has the following method:

#### .algorithm(self)

A python generator function that yields whenever it wants a Wall Clock protocol measurement to be taken:

```
candidateOrNone = yield timeoutSecs
```

The yield must pass a timeout in seconds. This is the maximum amount of time the Wall Clock client will wait for a response to its request before timing out.

Changed in version 0.4: The yield statement will return either None or a Candidate object representing the result of the measurement.

The algorithm can then use the Candidate object in its algorithm for estimating the wall clock (and in the case of most practical implementations: adjusting a clock object).

Here is an example of a simple naive algorithm that adjusts a *CorrelatedClock* object using the most recent measurement, irrespective of influencing factors such as previous measurements or network latency (round trip time). It makes requests at most once per second and has a timeout on waiting for responses of 0.5 seconds:

```
class NaiveAlgorithm(object):
    def __init__(self,clock):
        self.clock = clock

def algorithm(self):
    while True:
        candidate=(yield 0.5)
        if candidate is not None:
            self.clock.correlation = candidate.calcCorrelationFor(self.clock)
            time.sleep(1.0)
```

# Composable Filter and prediction algorithm

There is also a simple modular framework for building up an algorithm out of two parts:

- Filters processes measurement candidates, determining whether to reject them.
- A Predictor takes the measurement candidates outputted from the filtering step and use them to adjust the

Use the FilterAndPredict() function to compose zero, one or more Filters, and a Predictor into an algorithm that can be used with a WallClockClient.

Changed in version 0.4: When using this algorithm, you provide a *CorrelatedClock* object to it, whose parent is the clock given to the *WallClockClient*. This algorithm controls the *CorrelatedClock* object by settings its *correlation* property to that returned by the predictor. The parent of this clock is the clock used by the *WallClockClient* in generating the measurement candidates. So the job of the predictor is to determine the best correlation for modelling the relationship between that (parent) clock and the wall clock of the server.

Here is a simple example that uses a simple predictor and a round-trip-time threshold filter:

The Clock object given to the algorithm must be CorrelatedClock whose parent is the clock object provided to the WallClockClient object.

#### Round-trip time threshold Filter

The FilterRttThreshold class implements a filter that eliminates any candidate where the round-trip time exceeds a threshold.

#### Lowest dispersion candidate filter

The FilterLowestDispersionCandidate class implements a filter that eliminates any candidate if it does not have a lower dispersion that any candidate that came before it.

#### **Simple Predictor**

The PredictSimple class is a simple predictor that uses the candidate most recently provided to it and directly transforms that into a dybcss.clock.Correlation.

## Writing your own Filter

You can write your own Filter by creating a class with the following method defined:

.checkCandidate(self, candidate)

**Parameters candidate** – A (dict) containing two *Candidate* objects representing the result of the measurement in units of ticks (dict key "ticks") and units of nanoseconds (dict key "nanos"):

# Writing your own Predictor

You can write your own Predictor by creating a class with the following methods defined:

.addCandidate (self, candidate)

**param candidate** A (dict) containing two *Candidate* objects representing the result of the measurement in units of of nanoseconds.

This method is called whenever a measurement candidate resulting from a requestresponse measurement survives the filtering process.

.predictCorrelation(self)

Returns A Correlation

The returned Correlation must represent the relationship between the clock and its parent, such that the clock becomes an estimate of the server's Wall Clock. This must be in the correct units (tick rate) for the clock and its parent.

#### **Classes**

#### WallClockClient

class dvbcss.protocol.client.wc.WallClockClient

Simple object implementing the client side of the CSS-TS protocol.

Use by initialising and supplying with an algorithm object and Clock object.

The Candidate objects provided to the algorithm represent the relationship between the parent of the provided clock and the server's Wall Clock.

The algorithm is then expected to set the *dvbcss.clock.Correlation* of the clock object such that it becomes an estimate of the server's Wall Clock.

It is recommended to use the LowestDispersionCandidate algorithm.

#### **Initialisation takes the following parameters:**

## **Parameters**

• (bindaddr, bindport) – (str, int) A tuple containing the IP address (as a string) and port (as an int) to bind to to listen for incoming packets

- (dstaddr, dstport) (str, int) A tuple containing the IP address (as a string) and port (as an int) of the Wall Clock server
- wallClock (clock) The local clock that will be controlled to be a Wall Clock. Measurements will be taken from its parent and candidates provided to the algorithm will represent the relationship between that (parent) clock and the server's wall clock.
- wcAlgorithm (algorithm) The algorithm for the client to use to update the clock.

#### algorithm = None

(read only) The algorithm object being used with this WallClockClient

#### start(

Call this method to start the client running. This function call returns immediately and the client proceeds to run in a thread in the background.

Does nothing if the client is already running.

#### stop()

Call this method to stop the client running. Returns once the client has stopped.

If the client is not running then nothing happens and this call returns immediately.

# **Dispersion algorithm**

class dvbcss.protocol.client.wc.algorithm.LowestDispersionCandidate(clock,

repeat-Secs=1.0, timeout-Secs=0.2, local-MaxFreqErrorPpm=None)

Algorithm that selects the candidate (request-response measurement result) with the lowest dispersion.

Dispersion is a formal measure of the error bounds of the Wall Clock estimate. This value is the sum of possible error due to:

- •measurement precision limitations (at both client and server)
- •round-trip time
- •maximum potential for oscillator frequency error at the client and at the server server This grows as the candidate (that was used to most recently adjust the clock) ages.

**Note:** The Clock object must be the same one that is provided to the WallClockClient, otherwise this algorithm will not synchronise correctly.

The tick rate of the Clock can be any tick rate (it does not have to be one tick per nanosecond), but too low a tick rate will limit clock synchronisation precision.

There is a stub callback function provided that you can override (e.g. by subclassing) that will be called whenever the clock is adjusted:

•onClockAdjusted()

The arguments to this method provide details of when the adjustment took place and what adjustment was made. It also reports the dispersion before and after the adjustment and gives information needed to extrapolate future dispersions. You can use this, for example, to record the clock dispersion over time.

*Initialisation takes the following parameters:* 

#### **Parameters**

- clock A Correlated object representing that will be adjusted to match the Wall Clock.
- repeatSecs (float) The rate at which Wall Clock protocol requests are to be sent (in seconds).
- **timeoutSecs** (float) The timeout on waiting for responses to requests (in seconds).
- **localMaxFreqErrorPpm** Optional. Override using the getRootMaxFreqError() of the clock as the max freq error of the local clock, and instead use this value. It is the clock maximum frequency error in parts-per-million

#### getCurrentDispersion()

**Returns** Current dispersion at this moment in time in units of nanoseconds.

## getWorstDispersion()

Returns the worst (greatest) dispersion encountered since the previous time this method was called.

The first time it is called, the value reported will be very large, reflecting the fact that initially dispersion is high because the client is not yet synchronised.

#### **Returns** dispersion

onClockAdjusted (timeAfterAdjustment, adjustment, oldDispersionNanos, newDispersionNanos, dispersionGrowthRate)

This method is called immediately after a clock adjustment has been made, and gives details on how the clock was changed and the effect on the dispersion.

#### **Parameters**

- **timeAfterAdjustment** The wall clock time (in ticks) immediately after the adjustment took place
- adjustment The amount by which the wall clock instaneously changed (in ticks)
- oldDispersionNanos The dispersion (in nanoseconds) just prior to adjustment
- newDispersionNanos The dispersion (in nanoseconds) immediately after adjustment
- **dispersionGrowthRate** The rate at which dispersion will continue to grow.

**To calculate a future dispersion at time T:** futureDispersion = newDispersionNanos + (t-timeOfAdjustment) \* dispersionGrowthRate

This is a stub for this method. Sub-classes should implement it.

#### Most recent measurement algorithm

Simple (naive) Wall Clock client algorithm.

Crash locks the supplied clock based on the offset observed in the result of every successful request/response.

**Note:** The Clock object must be the same one that is provided to the WallClockClient, otherwise this algorithm will not synchronise correctly.

The tick rate of the Clock can be any tick rate (it does not have to be one tick per nanosecond), but too low a tick rate will limit clock synchronisation precision.

*Initialisation takes the following parameters:* 

#### **Parameters**

- clock A CorrelatedClock object representing that will be adjusted to match the Wall Clock.
- repeatSecs (float) The rate at which Wall Clock protocol requests are to be sent (in seconds).
- timeoutSecs (float) The timeout on waiting for responses to requests (in seconds).

#### qetCurrentDispersion()

Calling this method will always result in ValueError being raised.

Raises ValueError – This algorithm does not model clock synchronisation accuracy.

#### Filter and Prediction composable algorithms

#### **Filters**

class dvbcss.protocol.client.wc.algorithm.\_filterpredict.FilterRttThreshold(thresholdMillis=1.0)
Simple filter that rejects all candidates where round trip time exceeds a specified threshold.

**Parameters** thresholdMillis – (float) The threshold to use (in milliseconds)

Note that at initialisation, the clock's dispersion is forced to +infinity.

**Parameters** clock – A CorrelatedClock object representing that will be adjusted to match the Wall Clock.

# **Predictors**

class dvbcss.protocol.client.wc.algorithm.\_filterpredict.PredictSimple (clock) Simple naive predictor that chooses the correlation represented by the most recent candidate

**Parameters** clock – The CorrelatedClock that is to be set.

Note that this predictor does not actually set the clock. It just needs it in order to calculate the correct correlation for it.

#### **Functions**

# Filter and Prediction algorithm creator

dvbcss.protocol.client.wc.algorithm.FilterAndPredict(clock, repeatSecs=1.0, timeoutSecs=0.2, filters=[], predictor=None)

Combines zero, one or more Filters and a Predictor and returns an algorithm for a WallClockClient.

#### **Parameters**

- clock A CorrelatedClock object that will be adjusted to match the Wall Clock.
- **repeatSecs** (float) The rate at which Wall Clock protocol requests are to be sent (in seconds).
- **timeoutSecs** (float) The timeout on waiting for responses to requests (in seconds).
- filters (list of Filters) A list of zero, one or more Filters
- predictor (Predictor) The Predictor to use, or None to default to PredictSimple

This algorithm controls the *CorrelatedClock* object by settings its *correlation* property to that provided by the predictor.

The parent of this *clock* is the clock used by the *WallClockClient* in generating the measurement candidates. So the job of the predictor is always to estimate the *Correlation* needed by the *clock*.

Requests are made at the repetition rate specified. If a response is received within the timeout period it is then it is transformed into a measurement candidate and passed to the filters. Filters are applied in the order you list them. If a candidate survives filtering, then it is passed to the predictor. Every time a candidate is provided to the predictor, the correlation returned by the predictor replaces the previous correlation.

**Note:** The Clock object must be *CorrelatedClock* whose parent is the clock object that is measured when generating the candidates.

The tick rate of the Clock can be any tick rate (it does not have to be one tick per nanosecond), but too low a tick rate will limit clock synchronisation precision.

#### Candidate quality calculator

This function is used internally by the WallClockClient class.

```
dvbcss.protocol.client.wc.algorithm.calcQuality(reqMsg, respMsg)
```

Generate measure of how good the response was. Quality < 0 means response corresponded to a different request.

Quality = 3 or 4 means it was a response for which no follow-up is expected or a follow-up response.

Quality = 2 means it was a response for which a follow-up is expected

# **CSS-WC Servers**

- Classes
  - WallClockServer

Modules: dvbcss.protocol.server.wc

- Classes
  - WallClockServer

#### **Classes**

#### WallClockServer

This package provides objects for representing messages exchanged via the DVB CSS-WC protocol and for implementing clients and servers.

The WC protocol is a simple UDP request response-protocol that enables simple clock synchronisation algorithms to be used to establish a common *wall clock* between a server and client.

There is a WallClockServer class providing a self contained Wall Clock server. The WallClockClient is designed to allow different algorithms to be plugged in for acting on the results of the request-response interaction to adjust a local clock object to match the Wall Clock of the server.

Modules for using the CSS-WC protocol:

- dvbcss.protocol.wc: objects for representing and packing/unpacking the protocol messages.
- dvbcss.protocol.client.wc: implementation of a client for a CSS-WC connection.
- dvbcss.protocol.client.wc.algorithm: algorithms to be used with a CSS-WC client.
- dvbcss.protocol.server.wc: implementation of a server for a CSS-WC connection.

See Protocol server implementation details for information on how the servers are implemented.

# Common types and objects

# Signalling that a property is to be omitted from a message

```
dvbcss.protocol.OMIT object
```

When this object is assigned to an attribute of a protocol message object this indicates that the corresponding property is not included in the JSON representation of that message (it is omitted).

Here is an example. By default nearly all properties of a freshly created CII message object are 'OMIT':

```
>>> from dvbcss.protocol.cii import CII
>>> from dvbcss.protocol import OMIT

>>> c=CII()
>>> print repr(c.contentId)
OMIT

>>> c.wcUrl = "udp://192.168.1.1:6677"
>>> print repr(c.wcUrl)
'udp://192.168.1.1:6677'

>>> c.wcUrl = OMIT
>>> print repr(c.wcUrl)
OMIT
```

# **Private data**

Some protocol messages contain optional properties to carry private data.

Private data is encoded in message objects here as a list of dict objects where each has a key "type" whose value is a URI.

Each dict can contain any other keys and values you wish so long as they can be parsed by the python json module's encoder. For example:

# **Exceptions**

class dvbcss.protocol.client.ConnectionError

Exception that is raised when it was not possible to open a connection to a server.

# CHAPTER 3

# Clocks, Time and Scheduling modules

This library contains a range of tools for dealing with timing, clocks, and timelines and scheduling code to run at set times.

Contents:

# **Montonic time functions**

Module: dvbcss.monotonic\_time

- Example use
- Operating system implementation details
  - Windows
  - Mac OS X
  - Linux
- Functions
  - time(), timeMicros() and timeNanos()
  - sleep()

This module implements operating system specific access to high resolution monotonic system timers for the following operating systems:

- Windows 2000 Pro or later
- Linux
- Mac OS X

# "pydvbcss - a library implementing DVB protocols for Companion Screen Synchronisation, Release 0.4.1-release

It implements a time() function and sleep() function that work the same as the time.time() and time. sleep() functions in the python standard library.

It also adds a timeNanos() and timeMicros() variants that report time in units of nanoseconds or microseconds instead of seconds.

See operating system specific implementation details below to understand the limitations of the functions provided in this module.

**Note:** For all supported operating systems, the sleep() function is not guaranteed to use the same underlying timer as the time() and therefore should be considered inaccurate.

# **Example use**

```
>>> import dvbcss.monotonic_time as monotonic_time
>>> monotonic_time.time()
4695.582637038
>>> monotonic_time.timeNanos()
4700164952506L
>>> monotonic_time.timeMicros()
4703471405L
>>> monotonic_time.sleep(0.5) # sleep 1/2 second
```

# Operating system implementation details

The precision and accuracy of the clocks and sleep functions are dependent on the host operating system and hardware. This module can therefore provide no performance guarantees.

# **Windows**

Windows NT 5.0 (Windows 2000 Professional) or later is supported, including the cygwin environment.

The time () function and its variants are based on the QueryPerformanceCounter() high resolution timer system call. This clock is guaranteed to be monotonic and have 1 microsecond precision or better.

The sleep() function is based on the CreateWaitableTimer() and SetWaitableTimer() system calls.

Note that the sleep() function for Windows is not guaranteed to be accurate because it is not possible to create blocking (non polling) delays based on the clock source used. However it should have significantly higher precision than the standard 15ms windows timers and will be fine for short delays.

## Mac OS X

The time () function and its variants are based on the mach absolute time() system call.

The clock is guaranteed to be monotonic. Apple provides no guarantees on precision, however in practice it is usually based on hardware tick counters in the processor or support chips and so is extremely high precision (microseconds or better).

The sleep() function is based on the nanosleep() system call. It is unclear whether this uses the same underlying counter as mach\_absolute\_time().

#### Linux

The time() function and its variants are based on the  $clock\_gettime()$  system call requesting  $CLOCK\_MONOTONIC$ .

The sleep() function is based on the nanosleep() system call. It is unclear whether this uses the same underlying counter as *CLOCK MONOTONIC*.

## **Functions**

# time(), timeMicros() and timeNanos()

```
dvbcss.monotonic_time.time()
```

Return monotonic time in seconds and fractions of seconds (as a float). The precision is operating system dependent.

```
dvbcss.monotonic time.timeMicros()
```

Return monotonic time in integer microseconds. The precision is operating system dependent.

```
dvbcss.monotonic_time.timeNanos()
```

Return monotonic time in integer nanoseconds. The precision is operating system dependent.

# sleep()

```
dvbcss.monotonic\_time.sleep(t)
```

Sleep for specified number of second and fractions of seconds (as a float). The precision is operating system dependent.

**Throws TimeoutError** if the underlying system call used to sleep reported a timeout (OS dependent behaviour)

**Throws InterruptedException** if a signal or other interruption is received while sleeping (OS dependent behaviour)

**Note:** For all supported operating systems, the sleep() function is not guaranteed to use the same underlying timer as the time() and therefore should be considered inaccurate.

# Synthesised clocks (dvbcss.clock)

Module: dvbcss.clock

- Introduction
- Limitations on tick resolution (precision)
- Timers and Sleep functions
- Accounting for error (dispersion)
- Usage examples
  - Simple hierarchies of clocks

- Clock speed adjustment
- Translating tick values between clocks
- Implementing new clocks
- *Not a number (nan)*
- Functions
  - measurePrecision estimate measurement precision of a clock
- Classes
  - ClockBase base class for clocks
  - SysClock Clock based on time module
  - CorrelatedClock Clock correlated to another clock
  - OffsetClock A clock that is offset by a fixed amount of root time
  - TunableClock Clock with dynamically adjustable frequency and tick offset
  - RangeCorrelatedClock Clock correlated to another clock
  - Correlation represents a Correlation

The dvbcss.clock module provides software synthesised clock objects that can be chained together into dependent hierarchies. Use in conjunction with dvbcss.task to sleep and run code at set times on these clocks.

### Introduction

The classes in this module implement software synthesised clocks from which you can query a current time value. A clock counts in whole numbers of ticks (unlike the standard library time.time() function which counts in seconds and fractions of a second) and has a tick rate (expressed in ticks per second).

To use clocks as timers or to schedule code to run later, you must use them with the functions of the *dvbcss.task* module.

To use clocks begin with a root clock that is based on a underlying timing source. The following root clocks are provided:

SysClock is an root clock based on the dvbcss.monotonic\_time.time() function as the underlying time source

Other dependent clocks can then be created that have the underlying clock as their parent. and further dependent clocks can be created with those dependents as their parents, creating chains of clocks, each based on their parent and leading back to an underlying clock. The following dependent clocks are provided:

- CorrelatedClock is a fixed tick rate clock where you define the point of correlation between it and its parent.
- OffsetClock \*\* is a clock that is the same as its parent but with an offset amount of root time. Useful to calibrate for rendering pipeline delays.
- TunableClock is a clock that can have its tick count tweaked and its frequency slewed on the fly.
- RangleCorrelatedClock is a clock where the relationship to the parent is determined from two points of correlation.

Dependent clocks can have a different tick rate to their parent and count their ticks from a different starting point.

Dependent clocks allow their relationship to its parent clock to be changed dynamically - e.g. the absolute value, or the rate at which the clock ticks. If your code needs to be notified of such a change, it can bind itself as a dependent to that clock.

The base ClockBase class defines the set of methods common to all clocks (both underlying and dependent)

# **Limitations on tick resolution (precision)**

The Clock objects here do not run a thread that counts individual ticks. Instead, to determine the current tick value they query the parent clock for its current tick value and then calculate what the tick value should be.

A clock is therefore **limited in the precision and resolution of its tick value by its parents.** SysClock, for example, is limited by the resolution of the underlying time source provided to it by dvbcss.monotonic\_time module's dvbcss.monotonic\_time.time() function. And this will be operating system dependent. SysClock also outputs ticks as integer values.

If a parent of a clock only reports whole number (integer) tick values then that also limits the resolution of any clocks that depend on it. For example, a clock that counts in integer ticks only at 25 ticks per second will cause a clock descended from it, with a tick rate of 100 ticks per second, to report tick values that increment 4 ticks at a time ... or worse if a parent of both has an even lower tick rate.

With the clocks provided by this module, only SysClock limits itself to integer numbers of ticks. CorrelatedClock and TunableClock are capable of fractional numbers of ticks provided that the parameters provided to them (e.g. the tickRate) are passed as floating point values (this will force python to do the maths in floating point instead of integer maths).

# **Timers and Sleep functions**

Use the functions of the *dvbcss.task* in conjunction with Clock objects to create code that sleeps, or which triggers callbacks, based on time as measured by these clocks.

# **Accounting for error (dispersion)**

These clocks also support tracking and calculating error bounds on the values they report. This is known as dispersion. It is useful if, for example, a clock hierarchy is being used to estimate time based on imperfect measurements - such as when a companion tries to estimate the Wall Clock of a TV.

Each clock in a hierarchy makes its own contribution to the overall dispersion. When a clock is asked to calculate dispersion (using the dispersionAtTime() method), the answer it gives is the sum of the error contributions from itself and its parents, all the way back up to the root system clock.

A system clock has error bounds determined by the precision with which it can be measured (the smallest amount by which its values change).

When using a dependent clock, such as a *CorrelatedClock*, the correlation being used to set its relationship to its parent might also have some uncertainty in it. This information can be included in the *Correlation*. Uncertainty based on measurements/estimates can grow over time - e.g. because the clocks in a TV and companion gradually drift. So there are two parameters that you can provide in a *Correlation* - the *initial error* and the *growth rate*. As time passes, the error for the clock using this correlation is calculated as the initial error plus the growth rate multiplied by how much time has passed since the point of correlation.

# **Usage examples**

#### Simple hierarchies of clocks

Here is a simple example where a clock represents a timeline and another represents a timeline related to the first by a correlation:

At some point later in time during the program, we query the values of all the clocks, confirming that the sub timeline is always 100 ticks ahead of the base timeline.

Note that in these examples, for clarity, the tick count on the sysClock is artificially low. It would likely be a much larger value.

We then change the correlation for the base timeline, declaring tick 25 on its baseline to correspond to tick 0 on its parent timeline, and both the base timeline and the sub timeline reflect this:

```
>>> baseTimeline.correlation = Correlation(0,25)
>>> printTimes()
SysClock    ticks = 30000
Base timeline ticks = 775
Sub timeline ticks = 875
```

# Clock speed adjustment

All clocks have a speed property. Normally this is 1.0. Some clock classes support changing this value. This scales the rate at which the clock ticks relative to its parent. For example, 0.5 corresponds to half speed; 2.0 = double speed, 0 = frozen and -1.0 = reverse.

Clocks will take speed into account when returning their current tick position or converting it to or from the tick value of a parent clock. However it does not alter the tickRate property. A child clock will similarly ignore the speed property of a parent clock. In this way, the speed property can be used to tweak the speed of time, or to emulate speed control (fast forward, rewind, pause) for a media timeline.

Here is an example where we create 3 clocks in a chain and all tick initially at 100 ticks per second:

```
>>> import time
>>> baseClock = Sysclock(tickRate=100)
>>> clock1 = TunableClock(parent=baseClock, tickRate=100)
>>> clock2 = TunableClock(parent=clock1, tickRate=100)
```

We confirm that both clock1 and its child - clock2 - tick at 100 ticks per second:

```
>>> print clock1.ticks; time.sleep(1.0); print clock1.ticks
5023
5123
>>> print clock2.ticks; time.sleep(1.0); print clock2.ticks
2150
2250
```

If we change the tick rate of clock1 this affects clock1, but its child - clock2 - continues to tick at 100 ticks every second:

```
>>> clock1.tickRate = 200
>>> print clock1.ticks; time.sleep(1.0); print clock1.ticks
5440
5640
>>> print clock2.ticks; time.sleep(1.0); print clock2.ticks
4103
4203
```

But if we *instead* change the speed multiplier of clock1 then this not only affects the ticking rate of clock1 but also of its child - clock2:

```
>>> clock1.tickRate = 100
>>> clock1.speed = 2.0
>>> print clock1.ticks; time.sleep(1.0); print clock1.ticks
5740
5940
>>> print clock2.ticks; time.sleep(1.0); print clock2.ticks
4603
4803
```

# Translating tick values between clocks

The clock classes provide mechanisms to translate a tick value from one clock to a tick value of another clock such that it still represents the same moment in time. So long as both clocks share a common ancestor clock, the conversion will be possible.

toParentTicks() and fromParentTicks() converts tick values for a clock to/from its parent clock. toOtherClockTicks() will convert a tick value for this clock to the corresponding tick value for any other clock with a common ancestor to this one.

```
from dvbcss.clock import SysClock
from dvbcss.clock import CorrelatedClock
from dvbcss.clock import Correlation
```

```
# create a clock based on dvbcss.monotonic_time.time() that ticks in milliseconds
sysClock = SysClock(tickRate=1000)
                                  .-- | mediaClock |
# +----+ <---
# | sysClock | <-- | wallClock |
# +-----+ +-----+
                                 '-- | otherMediaClock |
#
                                     +----+
wallClock = CorrelatedClock(parentClock=sysClock, tickRate=1000000000,_
\rightarrowcorrelation=Correlation(0,0))
mediaClock = CorrelatedClock(parentClock=wallClock, tickRate=25,__
→correlation=Correlation(500021256, 0))
otherMediaClock = CorrelatedClock(parentClock=wallClock, tickRate=30,,,
→correlation=Correlation(21093757, 0))
# calculate wall clock time 'w' corresponding to a mediaClock time 1582:
t = 1582
w = mediaClock.toParentTicks(t)
print "When MediaClock ticks =", t, " wall clock ticks =", w
# calculate mediaClock time 'm' corresponding to wall clock time 1920395
w = 1920395
m = mediaClock.fromParentTicks(w)
print "When wall clock ticks =", w, " media clock ticks =", m
# calculate other media clock time corresponding to media clock time 2248
t = 2248
o = mediaClock.toOtherClockTicks(otherMediaClock, t)
print "When MediaClock ticks =", t, " other media clock ticks =", o
```

Let us now suppose that the wall clock is actually an estimate of a Wall Clock on another device. When we set the correlation we therefore include error information that is calculated from the proces by which the Wall Clock of the other device is estimated:

```
wallClock.correlation = Correlation(24524535, 34342, initialError=0.012, 

→errorGrowthRate=0.00005)
```

Here we are saying that the error bounds of the estimate at the point in time represented by the correlation is  $\pm$ 0.012 seconds. This will grow by 0.00005 seconds for every tick of the parent clock.

## Implementing new clocks

Implement a new clock class by subclassing ClockBase and implementing the stub methods.

For example, here is a clock that is the same as its parent (same tick rate) except that its current tick value differs by a fixed offset.

```
from dvbcss.clock import ClockBase
class FixedTicksOffsetClock(ClockBase):
    def __init__(self, parent, offset):
        super(FixedTicksOffsetClock, self).__init__()
        self._parent = parent
        self._offset = offset
   def calcWhen(self, ticksWhen):
        return self._parent.calcWhen(ticksWhen - self._offset)
    def fromParentTicks(self, ticks):
        return ticks + self._offset
    def getParent(self):
        return self._parent
    @property
   def tickRate(self):
        return self._parent.tickRate
    @property
   def ticks(self)
        return self._parent.ticks + self._offset
    def toParentTicks(self, ticks):
        return ticks - self._offset
    def _errorAtTime(self,t):
        return 0
```

In use:

```
>>> f = FixedTicksOffsetClock(parentClock, 100)
>>> print parentClock.ticks, f.ticks
216 316
```

When doing this, you must decide whether to allow the speed to be adjusted. If you do, then it must be taken into account in the calculations for the methods: calcWhen(), fromParentTicks() and toParentTicks().

# Not a number (nan)

"Not a number" value of a float. Check if a value is NaN like this:

```
>>> import math
>>> math.isnan(nanValue)
True
```

Converting tick values to a parent clock or to the root clock may result in this value being returned if one or more of the clocks involved has speed zero.

# **Functions**

#### measurePrecision - estimate measurement precision of a clock

dvbcss.clock.measurePrecision(clock, sampleSize=10000)

Do a very rough experiment to work out the precision of the provided clock.

Works by empirically looking for the smallest observable difference in the tick count.

**Parameters** sampleSize – (int) Number of iterations (sample size) to estimate the precision over

**Returns** (float) estimate of clock measurement precision (in seconds)

# **Classes**

#### ClockBase - base class for clocks

class dvbcss.clock.ClockBase(\*\*kwargs)

Base class for all clock classes.

By default, adjusting tickRate and speed are not permitted unless a subclass overrides and implements a property setter

bind(dependent)

Bind for notification if this clock changes.

**Parameters dependent** – When this clock changes, the *notify()* method of this dependent will be called, passing a single argument that is this clock.

calcWhen (ticksWhen)

**Return** "when" in terms of the underlying clock behind the root clock implementation (e.g. monotonic\_time.time() in the case of SysClock). Will return Not a number (nan) if the conversion is not possible (e.g. when current speed is zero and ticksWhen does not match the current correlation.childTicks).

This is a stub for this method. Sub-classes should implement it.

### clockDiff(otherClock)

Calculate the potential for difference between this clock and another clock.

**Parameters** otherClock – The clock to compare with.

**Returns** The potential difference in units of seconds. If effective speeds or tick rates differ, this will always be float ("+inf").

If the clocks differ in effective speed or tick rate, even slightly, then this means that the clocks will eventually diverge to infinity, and so the returned difference will equal +infinity.

New in version 0.4.

# dispersionAtTime(t)

Calculates the dispersion (maximum error bounds) at the specified clock time. This takes into account the contribution to error of this clock and its ancestors.

**Returns** Dispersion (in seconds) at the specified clock time.

New in version 0.4.

#### fromParentTicks(ticks)

This is a stub for this method. Sub-classes should implement it.

Method to convert from a tick value for this clock's parent to the equivalent tick value (representing the same point in time) for this clock.

Implementations should use the parent clock's tickRate and speed properties when performing the conversion.

**Returns** The specified tick value for the parent clock converted to the timescale of this clock.

Throws StopIteration if this clock has no parent

#### fromRootTicks(t)

Return the time for this clock corresponding to a given time of the root clock.

**Parameters** t – Tick value of the root clock.

**Returns** Corresponding tick value of this clock.

New in version 0.4.

## getAncestry()

Retrieve the ancestry of this clock as a list.

**Returns** A list of clocks, starting with this clock, and proceeding to its parent, then its parent's parent etc, ending at the root clock.

New in version 0.4.

#### getEffectiveSpeed()

Returns the 'effective speed' of this clock.

This is equal to multiplying together the speed properties of this clock and all of the parents up to the root clock.

#### getParent()

This is a stub for this method. Sub-classes should implement it.

**Returns** ClockBase representing the immediate parent of this clock, or None if it is a root clock.

#### getRoot()

**Returns** The root clock for this clock (or itself it has no parent).

New in version 0.4.

# getRootMaxFreqError()

Return potential error of underlying clock (e.g. system clock).

**Returns** The maximum potential frequency error (in parts-per-million) of the underlying root clock.

This is a partial stub method. It must be re-implemented by root clocks.

For a clock that is not the root clock, this method will pass through the call to the same method of the root clock.

New in version 0.4.

#### isAvailable()

Returns whether this clock is available, taking into account the availability of any (parent) clocks on which it depends.

**Returns** True if available, otherwise False.

New in version 0.4.

#### nanos

(read only) The tick count of this clock, but converted to units of nanoseconds, based on the current tick rate (but ignoring the *speed* property).

#### nanosToTicks (nanos)

Convert the supplied nanosecond to number of ticks given the current tick rate of this clock (but ignoring the *speed* property).

Parameters nanos – nanoseconds value

**Returns** number of ticks equivalent to the supplied nanosecond value

#### notify (cause)

Call to notify this clock that the clock on which it is based (its parent) has changed relative to the underlying timing source.

**Parameters** cause – The clock that is calling this method.

Will notify all dependents of this clock (entities that have registered themselves by calling bind()).

#### setAvailability (availability)

Set the availability of this clock.

**Parameters availability** – True if this clock is available, otherwise False.

If setting the availability of this clock changes the overall availability of this clock (as returned by <code>isAvailable()</code>) then dependents will be notified of the change.

New in version 0.4.

#### setParent (newParent)

This is a stub for this method. Sub-classes should implement it.

Change the parent of this clock (if supported). Will generate a notification of change.

#### speed

(read/write float) The speed at which the clock is running. Does not change the reported tickRate value, but will affect how ticks are calculated from parent clock ticks. Default = 1.0 = normal tick rate.

#### tickRate

(read only) The tick rate (in ticks per second) of this clock.

This is a stub for this method. Sub-classes should implement it.

#### ticks

(read only) The tick count for this clock.

This is a stub for this method. Sub-classes should implement it.

#### toOtherClockTicks (otherClock, ticks)

Converts a tick value for this clock into a tick value corresponding to the timescale of another clock.

Will return *Not a number (nan)* if the conversion is not possible (e.g. when current *speed* is zero and *ticksWhen* does not match the current *correlation.childTicks*).

#### **Parameters**

- **otherClock** A *clock* object representing another clock.
- ticks A time (tick value) for this clock

**Returns** The tick value of the *otherClock* that represents the same moment in time, or *Not a number (nan)* 

**Throws NoCommonClock** if there is no common ancestor clock (meaning it is not possible to convert

#### toParentTicks (ticks)

This is a stub for this method. Sub-classes should implement it.

Method to convert from a tick value for this clock to the equivalent tick value (representing the same point in time) for the parent clock.

Implementations should use the parent clock's tickRate and speed properties when performing the conversion.

**Returns** The specified tick value of this clock converted to the timescale of the parent clock.

Throws StopIteration if this clock has no parent

#### toRootTicks(t)

Return the time for the root clock corresponding to a given time of this clock.

Will return *Not a number (nan)* if the conversion is not possible (e.g. when current *speed* is zero and *ticksWhen* does not match the current *correlation.childTicks*).

**Parameters** t – Tick value for this clock.

**Returns** Corresponding tick value of the root clock, or *Not a number (nan)* 

New in version 0.4.

#### unbind(dependent)

Unbind from notification if this clock changes.

**Parameters** dependent – The dependent to unbind from receiving notifications.

### SysClock - Clock based on time module

class dvbcss.clock.SysClock (tickRate=1000000, maxFreqErrorPpm=500, \*\*kwargs)

A clock based directly on the standard library timer function monotonic\_time(). Returns *integer* ticks when its *ticks* property is queried.

The default tick rate is 1 million ticks per second, but a different tick rate can be chosen during initialisation.

#### Parameters

- tickRate Optional (default=1000000). The tick rate of this clock (ticks per second).
- maxFreqErrorPpm Optional (default=500). The maximum frequency error (in units of parts-per-million) of the clock, or an educated best-estimate of it.

The precision is automatically estimated using the *measurePrecision()* function when this clock is created. So creating a SysClock, particularly one with a low tickrate, may incur a noticeable delay at initialisation.

The measured precision is then reported as the dispersion of this clock.

It is not permitted to change the tickRate or speed property of this clock because it directly represents a system clock.

**Parameters** tickRate – (int) tick rate for this clock (in ticks per second)

#### bind(dependent)

Bind for notification if this clock changes.

**Parameters** dependent – When this clock changes, the notify() method of this dependent will be called, passing a single argument that is this clock.

#### calcWhen (ticksWhen)

**Return** "when" in terms of the underlying clock behind the root clock implementation (e.g. monotonic\_time.time() in the case of SysClock). Will return Not a number (nan) if the conversion is not possible (e.g. when current speed is zero and ticksWhen does not match the current correlation.childTicks).

(Documentation inherited from ClockBase)

#### clockDiff(otherClock)

Calculate the potential for difference between this clock and another clock.

**Parameters** otherClock – The clock to compare with.

**Returns** The potential difference in units of seconds. If effective speeds or tick rates differ, this will always be float ("+inf").

If the clocks differ in effective speed or tick rate, even slightly, then this means that the clocks will eventually diverge to infinity, and so the returned difference will equal +infinity.

New in version 0.4.

#### dispersionAtTime(t)

Calculates the dispersion (maximum error bounds) at the specified clock time. This takes into account the contribution to error of this clock and its ancestors.

**Returns** Dispersion (in seconds) at the specified clock time.

New in version 0.4.

#### fromParentTicks (ticks)

Method to convert from a tick value for this clock's parent to the equivalent tick value (representing the same point in time) for this clock.

Implementations should use the parent clock's tickRate and speed properties when performing the conversion.

**returns** The specified tick value for the parent clock converted to the timescale of this clock.

throws StopIteration if this clock has no parent

(Documentation inherited from ClockBase)

#### fromRootTicks(t)

Return the time for this clock corresponding to a given time of the root clock.

**Parameters** t – Tick value of the root clock.

**Returns** Corresponding tick value of this clock.

New in version 0.4.

#### getAncestry()

Retrieve the ancestry of this clock as a list.

**Returns** A list of clocks, starting with this clock, and proceeding to its parent, then its parent's parent etc, ending at the root clock.

New in version 0.4.

## getEffectiveSpeed()

Returns the 'effective speed' of this clock.

This is equal to multiplying together the speed properties of this clock and all of the parents up to the root clock.

# getParent()

**returns** ClockBase representing the immediate parent of this clock, or None if it is a root clock.

(Documentation inherited from ClockBase)

#### getRoot()

**Returns** The root clock for this clock (or itself it has no parent).

New in version 0.4.

#### getRootMaxFreqError()

Return potential error of underlying clock (e.g. system clock).

**returns** The maximum potential frequency error (in parts-per-million) of the underlying root clock.

This is a partial stub method. It must be re-implemented by root clocks.

For a clock that is not the root clock, this method will pass through the call to the same method of the root clock.

New in version 0.4.

(Documentation inherited from ClockBase)

#### isAvailable()

Returns whether this clock is available, taking into account the availability of any (parent) clocks on which it depends.

**Returns** True if available, otherwise False.

New in version 0.4.

#### nanos

(read only) The tick count of this clock, but converted to units of nanoseconds, based on the current tick rate (but ignoring the *speed* property).

#### nanosToTicks (nanos)

Convert the supplied nanosecond to number of ticks given the current tick rate of this clock (but ignoring the *speed* property).

**Parameters** nanos – nanoseconds value

Returns number of ticks equivalent to the supplied nanosecond value

#### notify(cause)

Call to notify this clock that the clock on which it is based (its parent) has changed relative to the underlying timing source.

**Parameters** cause – The clock that is calling this method.

Will notify all dependents of this clock (entities that have registered themselves by calling bind()).

#### setAvailability (availability)

SysClock is always available, and so availability cannot be set.

Raises NotImplementedError - Always raised.

New in version 0.4.

#### setParent (newParent)

This is a stub for this method. Sub-classes should implement it.

Change the parent of this clock (if supported). Will generate a notification of change.

#### speed

(read/write float) The speed at which the clock is running. Does not change the reported tickRate value, but will affect how ticks are calculated from parent clock ticks. Default = 1.0 = normal tick rate.

#### tickRate

(read only)The tick rate (in ticks per second) of this clock.

(Documentation inherited from ClockBase)

#### ticks

(read only) The tick count for this clock.

(Documentation inherited from ClockBase)

#### toOtherClockTicks (otherClock, ticks)

Converts a tick value for this clock into a tick value corresponding to the timescale of another clock.

Will return *Not a number (nan)* if the conversion is not possible (e.g. when current *speed* is zero and *ticksWhen* does not match the current *correlation.childTicks*).

#### **Parameters**

- otherClock A clock object representing another clock.
- ticks A time (tick value) for this clock

**Returns** The tick value of the *otherClock* that represents the same moment in time, or *Not a number (nan)* 

**Throws NoCommonClock** if there is no common ancestor clock (meaning it is not possible to convert

#### toParentTicks (ticks)

Method to convert from a tick value for this clock to the equivalent tick value (representing the same point in time) for the parent clock.

Implementations should use the parent clock's tickRate and speed properties when performing the conversion.

**returns** The specified tick value of this clock converted to the timescale of the parent clock.

throws StopIteration if this clock has no parent

(Documentation inherited from ClockBase)

#### toRootTicks(t)

Return the time for the root clock corresponding to a given time of this clock.

Will return *Not a number (nan)* if the conversion is not possible (e.g. when current *speed* is zero and *ticksWhen* does not match the current *correlation.childTicks*).

**Parameters** t – Tick value for this clock.

**Returns** Corresponding tick value of the root clock, or *Not a number (nan)* 

New in version 0.4.

#### unbind (dependent)

Unbind from notification if this clock changes.

**Parameters** dependent – The dependent to unbind from receiving notifications.

#### CorrelatedClock - Clock correlated to another clock


class dvbcss.clock.CorrelatedClock (parentClock, tickRate, correlation=Correlation(parentTicks=0, childticks=0, initialError=0, errorGrowthRate=0), speed=1.0, \*\*kwargs)

A clock locked to the tick count of the parent clock by a correlation and frequency setting.


Correlation is either a *Correlation* object or a simple tuple (*parentTicks*, *selfTicks*). The object form also allows you to specify error bounds information that this clock will track and propagate to other clocks.

When the parent clock ticks property has the value *parentTicks*, the ticks property of this clock shall have the value *selfTicks*.

This relationship can be illustrated as follows:



You can alter the correlation and tickRate and speed of this clock dynamically. Changes to tickRate and speed will not shift the point of correlation. This means that a change in tickRate or speed will probably cause the current tick value of the clock to jump. The amount it jumps by will be proportional to the distance the current time is from the point of correlation:



If you want a speed change to only affect the ticks from a particular point (e.g. the current tick value) onwards then you must re-base the correlation. There is a function provided to do that in some circumstances:

```
c = CorrelatedClock(parentClock=parent, tickRate=1000, correlation=(50,78))
    ... time passes ...
# now freeze the clock AT ITS CURRENT TICK VALUE
c.rebaseCorrelationAtTicks(c.ticks)
c.speed = 0
# now resume the clock but at half speed, but again without the tick value jumping
c.correlation = Correlation( parent.ticks, c.ticks )
c.speed = 0.5
```

**Note:** The maths to calculate and convert tick values will be performed, by default, as integer maths unless the parameters controlling the clock (tickRate etc) are floating point, or the ticks property of the parent clock supplies floating point values.

#### **Parameters**

- parentClock The parent clock for this clock.
- tickRate (int) tick rate for this clock (in ticks per second)
- **correlation** (*Correlation*) or tuple (*parentTicks*, *selfTicks*). The intial correlation for this clock.
- **speed** Initial speed for this clock.

#### bind(dependent)

Bind for notification if this clock changes.

**Parameters** dependent – When this clock changes, the *notify()* method of this dependent will be called, passing a single argument that is this clock.

#### calcWhen (ticksWhen)

**Return** "when" in terms of the underlying clock behind the root clock implementation (e.g. monotonic\_time.time() in the case of SysClock). Will return Not a number (nan) if the conversion is not possible (e.g. when current speed is zero and ticksWhen does not match the current correlation.childTicks).

(Documentation inherited from ClockBase)

#### clockDiff(otherClock)

Calculate the potential for difference between this clock and another clock.

**Parameters** otherClock – The clock to compare with.

**Returns** The potential difference in units of seconds. If effective speeds or tick rates differ, this will always be float ("+inf").

If the clocks differ in effective speed or tick rate, even slightly, then this means that the clocks will eventually diverge to infinity, and so the returned difference will equal +infinity.

New in version 0.4.

#### correlation

Read or change the correlation of this clock to its parent clock.

Assign a new Correlation object to change the correlation.

You can also pass a tuple (*parentTicks*, *selfTicks*) which will be converted to a correlation automatically. Reading this property after setting it with a tuple will return the equivalent *Correlation*.

#### dispersionAtTime(t)

Calculates the dispersion (maximum error bounds) at the specified clock time. This takes into account the contribution to error of this clock and its ancestors.

**Returns** Dispersion (in seconds) at the specified clock time.

New in version 0.4.

#### fromParentTicks (ticks)

Method to convert from a tick value for this clock's parent to the equivalent tick value (representing the same point in time) for this clock.

Implementations should use the parent clock's tickRate and speed properties when performing the conversion.

**returns** The specified tick value for the parent clock converted to the timescale of this clock.

throws StopIteration if this clock has no parent

(Documentation inherited from ClockBase)

#### fromRootTicks(t)

Return the time for this clock corresponding to a given time of the root clock.

**Parameters** t – Tick value of the root clock.

**Returns** Corresponding tick value of this clock.

New in version 0.4.

#### getAncestry()

Retrieve the ancestry of this clock as a list.

**Returns** A list of clocks, starting with this clock, and proceeding to its parent, then its parent's parent etc, ending at the root clock.

New in version 0.4.

#### getEffectiveSpeed()

Returns the 'effective speed' of this clock.

This is equal to multiplying together the speed properties of this clock and all of the parents up to the root clock.

#### getParent()

**returns** ClockBase representing the immediate parent of this clock, or None if it is a root clock.

(Documentation inherited from ClockBase)

#### getRoot()

**Returns** The root clock for this clock (or itself it has no parent).

New in version 0.4.

#### getRootMaxFreqError()

Return potential error of underlying clock (e.g. system clock).

**Returns** The maximum potential frequency error (in parts-per-million) of the underlying root clock.

This is a partial stub method. It must be re-implemented by root clocks.

For a clock that is not the root clock, this method will pass through the call to the same method of the root clock.

New in version 0.4.

#### isAvailable()

Returns whether this clock is available, taking into account the availability of any (parent) clocks on which it depends.

**Returns** True if available, otherwise False.

New in version 0.4.

#### $\verb|isChangeSignificant| (newCorrelation, newSpeed, thresholdSecs)|$

Returns True if the potential for difference in tick values of this clock (using a new correlation and speed) exceeds a specified threshold.

#### **Parameters**

- newCorrelation A Correlation
- **newSpeed** New speed as a float.

**Returns** True if the potential difference can/will eventually exceed the threshold.

This is implemented by applying a threshold to the output of quantifyChange().

New in version 0.4.

#### nanos

(read only) The tick count of this clock, but converted to units of nanoseconds, based on the current tick rate (but ignoring the *speed* property).

#### nanosToTicks (nanos)

Convert the supplied nanosecond to number of ticks given the current tick rate of this clock (but ignoring the *speed* property).

**Parameters** nanos – nanoseconds value

**Returns** number of ticks equivalent to the supplied nanosecond value

#### notify (cause)

Call to notify this clock that the clock on which it is based (its parent) has changed relative to the underlying timing source.

**Parameters** cause – The clock that is calling this method.

Will notify all dependents of this clock (entities that have registered themselves by calling bind()).

#### quantifyChange (newCorrelation, newSpeed)

Calculate the potential for difference in tick values of this clock if a different correlation and speed were to be used.

#### **Parameters**

- newCorrelation A Correlation
- newSpeed New speed as a float.

**Returns** The potential difference in units of seconds. If speeds differ, this will always be float ("+inf").

If the new speed is different, even slightly, then this means that the ticks reported by this clock will eventually differ by infinity, and so the returned value will equal +infinity. If the speed is unchanged then the returned value reflects the difference between old and new correlations.

New in version 0.4.

#### rebaseCorrelationAtTicks(tickValue)

Changes the *correlation* property to an equivalent correlation (that does not change the timing relationship between parent clock and this clock) where the tick value for this clock is the provided tick value.

#### setAvailability (availability)

Set the availability of this clock.

**Parameters availability** – True if this clock is available, otherwise False.

If setting the availability of this clock changes the overall availability of this clock (as returned by <code>isAvailable()</code>) then dependents will be notified of the change.

New in version 0.4.

#### setCorrelationAndSpeed (newCorrelation, newSpeed)

Set both the correlation and the speed to new values in a single operation. Generates a single notification for descendents as a result.

#### **Parameters**

- newCorrelation A *Correlation* representing the new correlation. Or a tuple (parentTicks, selfTicks) representing the correlation.
- **newSpeed** New speed as a float.

New in version 0.4.

#### setParent (newParent)

Change the parent of this clock (if supported). Will generate a notification of change.

(Documentation inherited from ClockBase)

#### speed

(read/write float) The speed at which the clock is running. Does not change the reported tickRate value, but will affect how ticks are calculated from parent clock ticks. Default = 1.0 = normal tick rate

(Documentation inherited from ClockBase)

#### tickRate

Read or change the tick rate (in ticks per second) of this clock. The value read is not affected by the value of the *speed* property.

#### ticks

(read only) The tick count for this clock.

(Documentation inherited from ClockBase)

#### toOtherClockTicks (otherClock, ticks)

Converts a tick value for this clock into a tick value corresponding to the timescale of another clock.

Will return *Not a number (nan)* if the conversion is not possible (e.g. when current *speed* is zero and *ticksWhen* does not match the current *correlation.childTicks*).

#### **Parameters**

- **otherClock** A *clock* object representing another clock.
- ticks A time (tick value) for this clock

**Returns** The tick value of the *otherClock* that represents the same moment in time, or *Not a number (nan)* 

Throws NoCommonClock if there is no common ancestor clock (meaning it is not possible to convert

#### toParentTicks(ticks)

Method to convert from a tick value for this clock to the equivalent tick value (representing the same point in time) for the parent clock.

Implementations should use the parent clock's tickRate and speed properties when performing the conversion.

**returns** The specified tick value of this clock converted to the timescale of the parent clock.

throws StopIteration if this clock has no parent

(Documentation inherited from ClockBase)

#### toRootTicks(t)

Return the time for the root clock corresponding to a given time of this clock.

Will return *Not a number (nan)* if the conversion is not possible (e.g. when current *speed* is zero and *ticksWhen* does not match the current *correlation.childTicks*).

**Parameters** t – Tick value for this clock.

**Returns** Corresponding tick value of the root clock, or *Not a number (nan)* 

New in version 0.4.

#### unbind (dependent)

Unbind from notification if this clock changes.

**Parameters** dependent – The dependent to unbind from receiving notifications.

#### OffsetClock - A clock that is offset by a fixed amount of root time

```
class dvbcss.clock.OffsetClock (parentClock, offset=0)
```

A clock that applies an offset such that reading it is the same as reading its parent, but as if the current time is slightly offset by an amount ahead (+ve offset) or behind (-ve offset).

OffsetClock inherits the tick rate of its parent. Its speed is always 1. It takes the effective speed into account when applying the offset, so it should always represent the same amount of time according to the root clock. In practice this means it will be a constant offset amount of real-world time.

This can be used to compensate for rendering delays. If it takes N seconds to render some content and display it, then a positive offset of N seconds will mean that the rendering code thinks time is N seconds ahead of where it is. It will then render the correct content that is needed to be displayed in N seconds time.

For example: A correlated clock (the "media clock") represents the time position a video player needs to currently be at.

The video player has a 40 milisecond (0.040 second) delay between when it renders a frame and the light being emitted by the display. We therefore need the video player to render 40 milliseconds in advance of when the frame is to be displayed. An OffsetClock is used to offset time in this way and is passed to the video player:

```
mediaClock = CorrelatedClock(...)

PLAYER_DELAY_SECS = 0.040
oClock = OffsetClock(parent=mediaClock, offset=PLAYER_DELAY_SECS)

videoPlayer.syncToClock(oClock)
```

If needed, the offset can be altered at runtime, by setting the offset property. For example, perhaps it needs to be changed to a 50 millisecond offset:

```
oClock.offset = 0.050
```

Both positive and negative offsets can be used.

bind(dependent)

Bind for notification if this clock changes.

**Parameters** dependent – When this clock changes, the notify() method of this dependent will be called, passing a single argument that is this clock.

calcWhen (ticksWhen)

**Return** "when" in terms of the underlying clock behind the root clock implementation (e.g. monotonic\_time.time() in the case of SysClock). Will return Not a number (nan) if the conversion is not possible (e.g. when current speed is zero and ticksWhen does not match the current correlation.childTicks).

This is a stub for this method. Sub-classes should implement it.

#### clockDiff(otherClock)

Calculate the potential for difference between this clock and another clock.

**Parameters** otherClock – The clock to compare with.

**Returns** The potential difference in units of seconds. If effective speeds or tick rates differ, this will always be float ("+inf").

If the clocks differ in effective speed or tick rate, even slightly, then this means that the clocks will eventually diverge to infinity, and so the returned difference will equal +infinity.

New in version 0.4.

#### dispersionAtTime(t)

Calculates the dispersion (maximum error bounds) at the specified clock time. This takes into account the contribution to error of this clock and its ancestors.

**Returns** Dispersion (in seconds) at the specified clock time.

New in version 0.4.

#### fromParentTicks(ticks)

Method to convert from a tick value for this clock's parent to the equivalent tick value (representing the same point in time) for this clock.

Implementations should use the parent clock's tickRate and speed properties when performing the conversion.

**returns** The specified tick value for the parent clock converted to the timescale of this clock.

throws StopIteration if this clock has no parent

(Documentation inherited from ClockBase)

#### fromRootTicks(t)

Return the time for this clock corresponding to a given time of the root clock.

**Parameters** t – Tick value of the root clock.

**Returns** Corresponding tick value of this clock.

New in version 0.4.

#### getAncestry()

Retrieve the ancestry of this clock as a list.

**Returns** A list of clocks, starting with this clock, and proceeding to its parent, then its parent's parent etc, ending at the root clock.

New in version 0.4.

#### getEffectiveSpeed()

Returns the 'effective speed' of this clock.

This is equal to multiplying together the speed properties of this clock and all of the parents up to the root clock.

#### getParent()

**returns** ClockBase representing the immediate parent of this clock, or None if it is a root clock.

(Documentation inherited from ClockBase)

#### getRoot()

**Returns** The root clock for this clock (or itself it has no parent).

New in version 0.4.

#### getRootMaxFreqError()

Return potential error of underlying clock (e.g. system clock).

**Returns** The maximum potential frequency error (in parts-per-million) of the underlying root clock.

This is a partial stub method. It must be re-implemented by root clocks.

For a clock that is not the root clock, this method will pass through the call to the same method of the root clock.

New in version 0.4.

#### isAvailable()

Returns whether this clock is available, taking into account the availability of any (parent) clocks on which it depends.

**Returns** True if available, otherwise False.

New in version 0.4.

#### nanos

(read only) The tick count of this clock, but converted to units of nanoseconds, based on the current tick rate (but ignoring the *speed* property).

#### nanosToTicks (nanos)

Convert the supplied nanosecond to number of ticks given the current tick rate of this clock (but ignoring the *speed* property).

Parameters nanos – nanoseconds value

**Returns** number of ticks equivalent to the supplied nanosecond value

#### notify(cause)

Call to notify this clock that the clock on which it is based (its parent) has changed relative to the underlying timing source.

Parameters cause – The clock that is calling this method.

Will notify all dependents of this clock (entities that have registered themselves by calling bind()).

#### offset

Read or change the number of seconds by which this clock is ahead (the offset).

#### setAvailability (availability)

Set the availability of this clock.

**Parameters** availability – True if this clock is available, otherwise False.

If setting the availability of this clock changes the overall availability of this clock (as returned by <code>isAvailable()</code>) then dependents will be notified of the change.

New in version 0.4.

#### setParent (newParent)

Change the parent of this clock (if supported). Will generate a notification of change.

(Documentation inherited from ClockBase)

#### speed

Read the clock's speed. It is always 1.

#### tickRate

Read the tick rate (in ticks per second) of this clock. The tick rate is always that of the parent clock.

#### ticks

(read only) The tick count for this clock.

(Documentation inherited from ClockBase)

#### toOtherClockTicks (otherClock, ticks)

Converts a tick value for this clock into a tick value corresponding to the timescale of another clock.

Will return *Not a number (nan)* if the conversion is not possible (e.g. when current *speed* is zero and *ticksWhen* does not match the current *correlation.childTicks*).

#### **Parameters**

- **otherClock** A *clock* object representing another clock.
- ticks A time (tick value) for this clock

**Returns** The tick value of the *otherClock* that represents the same moment in time, or *Not a number (nan)* 

**Throws NoCommonClock** if there is no common ancestor clock (meaning it is not possible to convert

#### toParentTicks (ticks)

Method to convert from a tick value for this clock to the equivalent tick value (representing the same point in time) for the parent clock.

Implementations should use the parent clock's tickRate and speed properties when performing the conversion.

**returns** The specified tick value of this clock converted to the timescale of the parent clock.

throws StopIteration if this clock has no parent

(Documentation inherited from ClockBase)

#### toRootTicks(t)

Return the time for the root clock corresponding to a given time of this clock.

Will return *Not a number (nan)* if the conversion is not possible (e.g. when current *speed* is zero and *ticksWhen* does not match the current *correlation.childTicks*).

**Parameters** t – Tick value for this clock.

**Returns** Corresponding tick value of the root clock, or *Not a number (nan)* 

New in version 0.4.

#### unbind (dependent)

Unbind from notification if this clock changes.

**Parameters** dependent – The dependent to unbind from receiving notifications.

#### TunableClock - Clock with dynamically adjustable frequency and tick offset

class dvbcss.clock.TunableClock (parentClock, tickRate, ticks=0, \*\*kwargs)

A clock whose tick offset and speed can be adjusted on the fly. Must be based on another clock.

Advancement of time of this clock is based on the tick count and rates reported by the supplied parent clock.

If you adjust the tickRate or speed, then the change is applied going forward from the moment it is made. E.g. if you are observing the rate of increase of the ticks property, then doubling the speed wil cause the ticks property to start increasing faster but will not cause it to suddenly jump value.

Changed in version 0.4: TunableClock has been reimplemented as a subclass of CorrelatedClock. The behaviour is the same as before, however it now also includes all the methods defined for CorrelatedClock too.

The maths to calculate and convert tick values will be performed, by default, as integer maths unless the parameters controlling the clock (tickRate etc) are floating point, or the ticks property of the parent clock supplies floating point values.

#### **Parameters**

- parentClock The parent clock for this clock.
- tickRate The tick rate (ticks per second) for this clock.
- **ticks** The starting tick value for this clock.

The specified starting tick value applies from the moment this object is initialised.

#### adjustTicks (offset)

Change the tick count of this clock by the amount specified.

#### **bind** (dependent)

Bind for notification if this clock changes.

**Parameters** dependent – When this clock changes, the notify() method of this dependent will be called, passing a single argument that is this clock.

#### calcWhen (ticksWhen)

**Return** "when" in terms of the underlying clock behind the root clock implementation (e.g. monotonic\_time.time() in the case of SysClock). Will return Not a number (nan) if the conversion is not possible (e.g. when current speed is zero and ticksWhen does not match the current correlation.childTicks).

(Documentation inherited from ClockBase)

#### clockDiff(otherClock)

Calculate the potential for difference between this clock and another clock.

**Parameters** otherClock – The clock to compare with.

**Returns** The potential difference in units of seconds. If effective speeds or tick rates differ, this will always be float ("+inf").

If the clocks differ in effective speed or tick rate, even slightly, then this means that the clocks will eventually diverge to infinity, and so the returned difference will equal +infinity.

New in version 0.4.

#### correlation

Read or change the correlation of this clock to its parent clock.

Assign a new Correlation object to change the correlation.

You can also pass a tuple (*parentTicks*, *selfTicks*) which will be converted to a correlation automatically. Reading this property after setting it with a tuple will return the equivalent *Correlation*.

#### dispersionAtTime(t)

Calculates the dispersion (maximum error bounds) at the specified clock time. This takes into account the contribution to error of this clock and its ancestors.

**Returns** Dispersion (in seconds) at the specified clock time.

New in version 0.4.

fromParentTicks (ticks)

Method to convert from a tick value for this clock's parent to the equivalent tick value (representing the same point in time) for this clock.

Implementations should use the parent clock's tickRate and speed properties when performing the conversion.

**returns** The specified tick value for the parent clock converted to the timescale of this clock

throws StopIteration if this clock has no parent

(Documentation inherited from ClockBase)

#### fromRootTicks(t)

Return the time for this clock corresponding to a given time of the root clock.

**Parameters** t – Tick value of the root clock.

**Returns** Corresponding tick value of this clock.

New in version 0.4.

#### getAncestry()

Retrieve the ancestry of this clock as a list.

**Returns** A list of clocks, starting with this clock, and proceeding to its parent, then its parent's parent etc, ending at the root clock.

New in version 0.4.

#### getEffectiveSpeed()

Returns the 'effective speed' of this clock.

This is equal to multiplying together the speed properties of this clock and all of the parents up to the root clock.

#### getParent()

**returns** *ClockBase* representing the immediate parent of this clock, or None if it is a root clock.

(Documentation inherited from ClockBase)

(Documentation inherited from CorrelatedClock)

#### getRoot()

**Returns** The root clock for this clock (or itself it has no parent).

New in version 0.4.

#### getRootMaxFreqError()

Return potential error of underlying clock (e.g. system clock).

**Returns** The maximum potential frequency error (in parts-per-million) of the underlying root clock.

This is a partial stub method. It must be re-implemented by root clocks.

For a clock that is not the root clock, this method will pass through the call to the same method of the root clock.

New in version 0.4.

#### isAvailable()

Returns whether this clock is available, taking into account the availability of any (parent) clocks on which it depends.

**Returns** True if available, otherwise False.

New in version 0.4.

#### isChangeSignificant (newCorrelation, newSpeed, thresholdSecs)

Returns True if the potential for difference in tick values of this clock (using a new correlation and speed) exceeds a specified threshold.

#### **Parameters**

- newCorrelation A Correlation
- **newSpeed** New speed as a float.

**Returns** True if the potential difference can/will eventually exceed the threshold.

This is implemented by applying a threshold to the output of quantifyChange().

New in version 0.4.

#### nanos

(read only) The tick count of this clock, but converted to units of nanoseconds, based on the current tick rate (but ignoring the *speed* property).

#### nanosToTicks(nanos)

Convert the supplied nanosecond to number of ticks given the current tick rate of this clock (but ignoring the *speed* property).

Parameters nanos - nanoseconds value

Returns number of ticks equivalent to the supplied nanosecond value

#### notify(cause)

Call to notify this clock that the clock on which it is based (its parent) has changed relative to the underlying timing source.

**Parameters** cause – The clock that is calling this method.

Will notify all dependents of this clock (entities that have registered themselves by calling bind()).

#### quantifyChange (newCorrelation, newSpeed)

Calculate the potential for difference in tick values of this clock if a different correlation and speed were to be used.

#### **Parameters**

- newCorrelation A Correlation
- newSpeed New speed as a float.

**Returns** The potential difference in units of seconds. If speeds differ, this will always be float ("+inf").

If the new speed is different, even slightly, then this means that the ticks reported by this clock will eventually differ by infinity, and so the returned value will equal +infinity. If the speed is unchanged then the returned value reflects the difference between old and new correlations.

New in version 0.4.

#### rebaseCorrelationAtTicks(tickValue)

Changes the *correlation* property to an equivalent correlation (that does not change the timing relationship between parent clock and this clock) where the tick value for this clock is the provided tick value.

#### setAvailability (availability)

Set the availability of this clock.

**Parameters** availability – True if this clock is available, otherwise False.

If setting the availability of this clock changes the overall availability of this clock (as returned by <code>isAvailable()</code>) then dependents will be notified of the change.

New in version 0.4.

#### setCorrelationAndSpeed (newCorrelation, newSpeed)

Set both the correlation and the speed to new values in a single operation. Generates a single notification for descendents as a result.

#### **Parameters**

- **newCorrelation** A *Correlation* representing the new correlation. Or a tuple (*parentTicks*, *selfTicks*) representing the correlation.
- newSpeed New speed as a float.

New in version 0.4.

#### setError (current, growthRate=0)

Set the current error bounds of this clock and the rate at which it grows per tick of the parent clock.

#### **Parameters**

- **current** Potential error (in seconds) of the clock at this time.
- growthRate Amount by which error will grow for every tick of the parent clock.

New in version 0.4.

#### setParent (newParent)

Change the parent of this clock (if supported). Will generate a notification of change.

(Documentation inherited from ClockBase)

#### slew

This is an alternative method of querying or adjusting the speed property.

The slew (in ticks per second) currently applied to this clock.

Setting this property will set the speed property to correspond to the specified slew.

For example: for a clock with tickRate of 100, then a slew of -25 corresponds to a speed of 0.75

#### speed

(read/write float) The speed at which the clock is running. Does not change the reported tickRate value, but will affect how ticks are calculated from parent clock ticks. Default = 1.0 = normal tick rate.

(Documentation inherited from ClockBase)

#### tickRate

Read or change the tick rate (in ticks per second) of this clock. The value read is not affected by the value of the *speed* property.

#### ticks

(read only) The tick count for this clock.

(Documentation inherited from ClockBase)

#### toOtherClockTicks (otherClock, ticks)

Converts a tick value for this clock into a tick value corresponding to the timescale of another clock.

Will return *Not a number (nan)* if the conversion is not possible (e.g. when current *speed* is zero and *ticksWhen* does not match the current *correlation.childTicks*).

#### **Parameters**

- otherClock A clock object representing another clock.
- ticks A time (tick value) for this clock

**Returns** The tick value of the *otherClock* that represents the same moment in time, or *Not a number (nan)* 

**Throws NoCommonClock** if there is no common ancestor clock (meaning it is not possible to convert

#### toParentTicks (ticks)

Method to convert from a tick value for this clock to the equivalent tick value (representing the same point in time) for the parent clock.

Implementations should use the parent clock's tickRate and speed properties when performing the conversion.

**returns** The specified tick value of this clock converted to the timescale of the parent clock.

throws StopIteration if this clock has no parent

(Documentation inherited from ClockBase)

#### toRootTicks(t)

Return the time for the root clock corresponding to a given time of this clock.

Will return *Not a number (nan)* if the conversion is not possible (e.g. when current *speed* is zero and *ticksWhen* does not match the current *correlation.childTicks*).

**Parameters** t – Tick value for this clock.

**Returns** Corresponding tick value of the root clock, or *Not a number (nan)* 

New in version 0.4.

#### unbind (dependent)


Unbind from notification if this clock changes.

**Parameters dependent** – The dependent to unbind from receiving notifications.

#### RangeCorrelatedClock - Clock correlated to another clock

A clock locked to the tick count of the parent clock by two different points of correlation.

This relationship can be illustrated as follows:



The tickRate you set is purely advisory - it is the tickRate reported to clocks that use this clock as the parent, and may differ from what the reality of the two correlations represents!

#### **Parameters**

- parentClock The parent clock for this clock.
- **tickRate** The advisory tick rate (ticks per second) for this clock.
- **correlation1** (*Correlation*) or tuple (*parentTicks*, *selfTicks*). The first point of correlation for this clock.
- **correlation2** (*Correlation*) or tuple (*parentTicks*, *selfTicks*). The second point of correlation for this clock.

#### bind(dependent)

Bind for notification if this clock changes.

**Parameters** dependent – When this clock changes, the notify() method of this dependent will be called, passing a single argument that is this clock.

#### calcWhen(ticksWhen)

**Return** "when" in terms of the underlying clock behind the root clock implementation (e.g. monotonic\_time.time() in the case of SysClock). Will return Not a number (nan) if the conversion is not possible (e.g. when current speed is zero and ticksWhen does not match the current correlation.childTicks).

(Documentation inherited from ClockBase)

#### clockDiff(otherClock)

Calculate the potential for difference between this clock and another clock.

Parameters otherClock - The clock to compare with.

**Returns** The potential difference in units of seconds. If effective speeds or tick rates differ, this will always be float ("+inf").

If the clocks differ in effective speed or tick rate, even slightly, then this means that the clocks will eventually diverge to infinity, and so the returned difference will equal +infinity.

New in version 0.4.

#### correlation1

Read or change the first correlation of this clock to its parent clock.

Assign a new Correlation or tuple (parentTicks, childTicks) to change the correlation.

#### correlation2

Read or change the first correlation of this clock to its parent clock.

Assign a new Correlation to change the correlation.

#### dispersionAtTime(t)

Calculates the dispersion (maximum error bounds) at the specified clock time. This takes into account the contribution to error of this clock and its ancestors.

**Returns** Dispersion (in seconds) at the specified clock time.

New in version 0.4.

#### fromParentTicks (ticks)

Method to convert from a tick value for this clock's parent to the equivalent tick value (representing the same point in time) for this clock.

Implementations should use the parent clock's tickRate and speed properties when performing the conversion.

**returns** The specified tick value for the parent clock converted to the timescale of this clock.

throws StopIteration if this clock has no parent

(Documentation inherited from ClockBase)

#### fromRootTicks(t)

Return the time for this clock corresponding to a given time of the root clock.

**Parameters** t – Tick value of the root clock.

**Returns** Corresponding tick value of this clock.

New in version 0.4.

#### getAncestry()

Retrieve the ancestry of this clock as a list.

**Returns** A list of clocks, starting with this clock, and proceeding to its parent, then its parent's parent etc, ending at the root clock.

New in version 0.4.

#### getEffectiveSpeed()

Returns the 'effective speed' of this clock.

This is equal to multiplying together the speed properties of this clock and all of the parents up to the root clock.

#### getParent()

**returns** ClockBase representing the immediate parent of this clock, or None if it is a root clock.

(Documentation inherited from ClockBase)

getRoot()

**Returns** The root clock for this clock (or itself it has no parent).

New in version 0.4.

#### getRootMaxFreqError()

Return potential error of underlying clock (e.g. system clock).

**Returns** The maximum potential frequency error (in parts-per-million) of the underlying root clock.

This is a partial stub method. It must be re-implemented by root clocks.

For a clock that is not the root clock, this method will pass through the call to the same method of the root clock.

New in version 0.4.

#### isAvailable()

Returns whether this clock is available, taking into account the availability of any (parent) clocks on which it depends.

**Returns** True if available, otherwise False.

New in version 0.4.

#### nanos

(read only) The tick count of this clock, but converted to units of nanoseconds, based on the current tick rate (but ignoring the *speed* property).

#### nanosToTicks (nanos)

Convert the supplied nanosecond to number of ticks given the current tick rate of this clock (but ignoring the *speed* property).

Parameters nanos – nanoseconds value

**Returns** number of ticks equivalent to the supplied nanosecond value

#### notify (cause)

Call to notify this clock that the clock on which it is based (its parent) has changed relative to the underlying timing source.

Parameters cause - The clock that is calling this method.

Will notify all dependents of this clock (entities that have registered themselves by calling bind()).

#### setAvailability (availability)

Set the availability of this clock.

**Parameters availability** – True if this clock is available, otherwise False.

If setting the availability of this clock changes the overall availability of this clock (as returned by <code>isAvailable()</code>) then dependents will be notified of the change.

New in version 0.4.

#### setParent (newParent)

Change the parent of this clock (if supported). Will generate a notification of change.

(Documentation inherited from ClockBase)

#### speed

(read/write float) The speed at which the clock is running. Does not change the reported tickRate value, but will affect how ticks are calculated from parent clock ticks. Default = 1.0 = normal tick rate.

(Documentation inherited from ClockBase)

#### tickRate

Read the tick rate (in ticks per second) of this clock. The value read is not affected by the value of the speed property.

#### ticks

(read only) The tick count for this clock.

(Documentation inherited from ClockBase)

#### toOtherClockTicks (otherClock, ticks)

Converts a tick value for this clock into a tick value corresponding to the timescale of another clock.

Will return *Not a number (nan)* if the conversion is not possible (e.g. when current *speed* is zero and *ticksWhen* does not match the current *correlation.childTicks*).

#### **Parameters**

- otherClock A clock object representing another clock.
- ticks A time (tick value) for this clock

**Returns** The tick value of the *otherClock* that represents the same moment in time, or *Not a number (nan)* 

**Throws NoCommonClock** if there is no common ancestor clock (meaning it is not possible to convert

#### toParentTicks(ticks)

Method to convert from a tick value for this clock to the equivalent tick value (representing the same point in time) for the parent clock.

Implementations should use the parent clock's tickRate and speed properties when performing the conversion.

**returns** The specified tick value of this clock converted to the timescale of the parent clock.

throws StopIteration if this clock has no parent

(Documentation inherited from ClockBase)

#### toRootTicks(t)

Return the time for the root clock corresponding to a given time of this clock.

Will return *Not a number (nan)* if the conversion is not possible (e.g. when current *speed* is zero and *ticksWhen* does not match the current *correlation.childTicks*).

**Parameters** t – Tick value for this clock.

**Returns** Corresponding tick value of the root clock, or *Not a number (nan)* 

New in version 0.4.

#### unbind (dependent)

Unbind from notification if this clock changes.

**Parameters** dependent – The dependent to unbind from receiving notifications.

#### **Correlation - represents a Correlation**

class dvbcss.clock.Correlation (parentTicks, childTicks, initialError=0, errorGrowthRate=0)

Immutable object representing a correlation. This can also optionally include bounds for the potential for error if the correlation is used to model a clock.

The correlation (*parentTicks*, *ticks*) represents a relationship between a (child) clock and its parent. The time *parentTicks* of the parent corresponds to the time *ticks* of the child.

#### **Parameters**

- parentTicks Time of the parent clock.
- **childTcks** Corresponding time of the clock using this correlation.
- initialError Optional (default=0). The amount of potential error (in seconds) at the moment represented by the correlation.
- **errorGrowthRate** Optional (default=0). The rate of growth of error (e.g. how many seconds error increases by per second of the parent clock)

This class is intended to be immutable. Instead of modifying a correlation, create a new one based on an existing one. The butWith() method is designed to assist with this.

..note:

```
For backwards compatibility with pydvbcss v0.3 and earlier, this object can also be treated as if it is a tuple (parentTicks, childTicks), for example:

..code-block:: python

c = Correlation(1,5, 0.1, 0.005)

# unapacking using an expression assignment parentTicks, childTicks = c

# accessing by index parentTicks = c[0] childTicks = c[1]
```

New in version 0.4.

**butWith** (*parentTicks=None*, *childTicks=None*, *initialError=None*, *errorGrowthRate=None*) Return a new correlation the same as this one but with the specified changes.

#### **Parameters**

- parentTicks Optional. A new Time of the parent clock.
- **childTcks** Optional. The corresponding time of the clock using this correlation.
- **initialError** Optional. The amount of potential error (in seconds) at the moment represented by the correlation.
- **errorGrowthRate** Optional. The rate of growth of error (e.g. how many seconds error increases by per second of the parent clock)

**Returns** New Correlation based on this one, but with the changes specified by the parameters.

If a parameter is set to *None* or not provided, then the existing value is taken from this correlation object.

#### childTicks

Number representing a time of the child clock, that corresponds to the *parentTicks* time of the parent clock.

#### errorGrowthRate

Number representing the amount that the potential for error will grow by (in units of seconds) for every tick of the parent clock. Default value is 0 if not set.

#### initialError

Number representing the amount of potential error (in units of seconds) at the moment represented by the correlation. Default value is 0 if not set.

#### parentTicks

Number representing a time of the parent clock.

## Task scheduling for clocks

Module: dvbcss.task

- Introduction
- Example
- Functions

#### Introduction

The *dvbcss.task* module provides sleep and scheduling functions for use with the *dvbcss.clock* module. These functions track adjustments to clocks (such as changes in the tick rate or tick value/offset) to ensure that the sleep or scheduled event happen when the clock actually reaches the target tick count value.

To use this module, just import it and directly call the functions sleepFor(), sleepUntil(), scheduleEvent() or runAt().

**Note:** Scheduling happens on a single thread, so if you use the runAt () function, try to keep the callback code as fast and simple as possible, so that it returns control as quickly as possible.

See *How the dvbcss.task module works internally* for information on how the internals of the Task module work.

#### **Example**

A simple example:

```
from dvbcss.clock import SysClock
from dvbcss.clock import CorrelatedClock
from dvbcss.task import sleepFor, runAt

s = SysClock()
c = CorrelatedClock(parentClock=s, tickRate=1000)

# wait 1 second
sleepFor(c, numTicks=1000)

# schedule callback in 5 seconds
def foo(message):
```

#### **Functions**

dvbcss.task.sleepUntil(clock, whenTicks)

Sleep until the specified clock reaches the specified tick value.

#### **Parameters**

- clock (dvbcss.clock.ClockBase) Clock to sleep against the ticks of.
- whenTicks (int) The tick value of the clock at which this function returns.

Returns after the specified tick value is reached.

```
dvbcss.task.sleepFor(clock, numTicks)
```

Sleep for the number of ticks of the specified clock.

#### **Parameters**

- clock (dvbcss.clock.ClockBase) Clock to sleep against the ticks of.
- **numTicks** (int) The number of ticks to sleep for.

Returns after the elapsed number of ticks of the specified clock have passed.

```
dvbcss.task.scheduleEvent (clock, whenTicks, event)
```

Schedule the threading. Event to be called when the specified clock reaches (or passes) the specified tick value.

#### **Parameters**

- clock (dvbcss.clock.ClockBase) Clock to schedule the event against
- whenTicks (int) The tick value of the clock at which the event is to be triggered.
- event (threading.Event) python Event object that the :method:threading.Event.set method will be called on at the scheduled time

```
dvbcss.task.runAt (clock, whenTicks, callBack, args=None, kwargs=None)
```

Call the specified callback function when the specified clock reaches (or passes) the specified tick value.

The callback happens on the single thread used within the clock scheduling system. You should avoid writing code that hogs this thread to do substantial processing.

#### **Parameters**

- clock (dvbcss.clock.ClockBase) Clock to schedule the callback against
- **whenTicks** (int) The tick value of the clock at which the callback is to be called.
- callback (callable) Function to be called
- args A list of positional arguments to be passed to the callback function when it is called.

• **kwargs** - A dict of keyword arguments to be pased to the callback function when it is called.

The <code>dvbcss.monotonic\_time</code> module provides a <code>time()</code> and <code>sleep()</code> functions equivalent to those in the standard python library time module. However these are guaranteeed to be monotonic and use the highest precision time sourcess available (depending on the host operating system).

The <code>dvbcss.clock</code> module provides high level abstractions for representing clocks and timelines and the relationships between them. The <code>client</code> and <code>server</code> implementations for the DVB-CSS protocols use these objects to represent clocks and timelines.

The:mod: *Task* module provides sleep and task scheduling functions that work with clock objects and allow code to be called when a clock reaches a particular tick value, even if that clock is adjusted in some way after the task is scheduled.

		n Screen Synchro	

# CHAPTER 4

Internal implementation details

## **Protocol server implementation details**

- CSS-WC
  - Overview
  - Classes
- CSS-CII and CSS-TS
  - Overview
  - Classes

#### **CSS-WC**

#### **Overview**

The CSS-WC server is based on a simple generic framework for building UDP servers

#### Classes

#### **CSS-CII and CSS-TS**

Module: dvbcss.protocol.server

#### Overview

The CSS-CII and CSS-TS servers subclass the WebSocket server functionality for cherrypy implemented by ws4py in the cherrypyserver module.

CIIServer and TSServer both inherit from a common base implementation WSServerTool provided in the *dvbcss.protocol.server* module.

The Tool provides the hook into cherrypy for handling the connection request and upgrading it to a WebSocket connection, spawning an object representing the WebSocket connection and which implements the WebSocket protocols.

The base server object class is intended to manage all WebSocket connections for a particular server endpoint. It therefore provides its own customised WebScoket class that is bound to that particular server object instance.

The tool is enabled via an "on" configuration when setting up the mount point in cherrypy. The tool also expects to a "handler\_cls" property set in the configuration at the mount point. This property points to a WebSocket class which can be instantiated to handle the connection.

Example usage: creating a server at "ws://<host>:80/endpoint" just using the base classes provided here:

```
import cherrypy
from ws4py.server.cherrypyserver import WebSocketPlugin
from dvbcss.protocol.server import WSServerBase, WSServerTool
# plug the tool into cherrypy as "my_server"
cherrypy.tools.my_server = WSServerTool()
WebSocketPlugin(cherrypy.engine).subscribe()
# create my server
myServer = WSServerBase()
# bind it to the URL path /endpoint in the cherrypy server
class Root (object):
    @cherrypy.expose
   def endpoint(self):
       pass
cfg = {"/endpoint": {'tools.my_server.on': True,
                'tools.my_server.handler_cls': myServer.handler
      }
cherrypy.tree.mount(Root(), "/", config=cfg)
# activate cherrypy web server on port 80
cherrypy.config.update({"server.socket_port":80})
cherrypy.engine.start()
```

See documentation for WSServerBase for information on creating subclasses to implement specific endpoints.

#### **Classes**

#### class .WebSocketHandler(WebSocket)

This class is created and returned by the WSServerBase.\_makeHandlerClass() method and each class returned is bound to the instance of WSServerBase that created it.

It is intended to be provided to cherrypy as the "handler\_cls" configuration parameter for the WebSocket tool. It is instantiated for every connection made.

These are subclasses of the ws4py WebSocket class and represent an individual WebSocket connection.

Instances of this class call through to WSServerBase.\_addConnection() and WSServerBase.\_removeConnection() and WSServerBase.\_receivedMessage() to inform the parent server of the WebSocket opening, closing and receiving messages.

classmethod is Enabled(cls)

**Returns** True if the server endpoint is enabled, otherwise False.

 ${f class}$  method canAllocateConnection (cls)

**Returns** True only if the connection limit of the parent server has not yet been reached. Otherwise False.

id(self)

**Returns** A human readable connection ID

### How the dvbcss.task module works internally

#### Introduction

The *dvbcss.task* module internally implements a task scheduler based around a single daemon thread with an internal priority queue.

Sleep and callback methods cause a task objet to be queued. The scheduler picks up the queued task and adds it to the priority queue and binds to the Clock so that it is notified of adjustments to the clock. When a task is added to the queue, the clock is queried to calculate the true time at which the tick count is expected to be reached by calling dvbcss.clock.ClockBase.calcWhen()

If a clock is adjusted the affected tasks are marked as deprecated (but remain in the priority queue) and new tasks are rescheduled with a recalculated time.

When one of the clocks involved has speed 0, then it may not be possible to calculate the time at which the task is to be scheduled. This happens when <code>dvbcss.clock.ClockBase.calcWhen()</code> returns *Not a number (nan)*. The task will not be immediately added to the priority queue, however it will be added later once the clock speed returns to a non-zero value. This happens automatically as part of the rescheduling process when a clock is adjusted.

#### **Objects**

dvbcss.task.scheduler = <dvbcss.task. Scheduler object>

Task scheduler. Starts an internal threading. Thread with theading. Thread.daemon set to True.

This is an internal of the Task module. For normal use you should not need to access it.

#### Variables

- taskheap the priority queue of tasks
- addQueue threadsafe queue of tasks to be added to the priority queue
- rescheduleQueue thereadsafe queue of clocks that have been adjusted and therefore which need to trigger rescheduling of tasks
- updateEvent theading. Event used to wake the scheduler thread whenever there is work pending (items added to addQueue or rescheduleQueue)
- clock\_Tasks mapping of clocks to takss that depend on them

Running instance of the dvbcss.task. Scheduler

#### Classes

```
class dvbcss.task._Scheduler(*args, **kwargs)
```

Task scheduler. Starts an internal threading. Thread with theading. Thread.daemon set to True.

This is an internal of the Task module. For normal use you should not need to access it.

#### **Variables**

- taskheap the priority queue of tasks
- addQueue threadsafe queue of tasks to be added to the priority queue
- rescheduleQueue thereadsafe queue of clocks that have been adjusted and therefore which need to trigger rescheduling of tasks
- updateEvent theading. Event used to wake the scheduler thread whenever there is work pending (items added to addQueue or rescheduleQueue)
- clock\_Tasks mapping of clocks to takes that depend on them

Starts the scheduler thread at initialisation.

#### notify(causeClock)

Callback entry point for when a clock is adjusted

**Parameters causeClock** – (*dvbcss.clock.ClockBase*) The clock that was adjusted and is therefore causing this notification of adjustment.

#### run()

Main runloop of the scheduler.

#### While looping:

1. Checks the queue of tasks to be added to the scheduler

The time the task is due to be executed is calculated and used as the sort key when the task is inserted into a priority queue.

2. Checks any queued requests to reschedule tasks (due to clock adjustments)

The existing task in the scheduler priority queue is "deprecated" And a new task is scheduled with the revised time of execution

3.checks any tasks that need to now be executed

Dequeues them and executes them, or ignores them if they are marked as deprecated

schedule (clock, whenTicks, callBack, args, kwargs)

Queue up a task for scheduling

#### **Parameters**

- clock (dvbcss.clock.ClockBase) the clock against which the task is scheduled
- whenTicks (int) The tick value of the clock at which the scheduled task is to be executed
- callback (func) The function (the task) that will be called at the scheduled time
- args (list) List of arguments to be passed to the function when it is invoked

 kwargs – (dict) Dictionary of keyword arguments to be passed to the function when it is invoked

#### stop()

Stops the scheduler if it is running.

**class** dvbcss.task.\_**Task** (*clock*, *whenTicks*, *callBack*, *args*, *kwargs*, *n*=0)

Representation of a scheduled task. This is an internal of the Task module. For normal use you should not need to acess it.

Initialiser

#### **Parameters**

- clock (dvbcss.clock.ClockBase) the clock against which the task is scheduled
- whenTicks (int) The tick value of the clock at which the scheduled task is to be executed
- callback (func) The function (the task) that will be called at the scheduled time
- args (list) List of arguments to be passed to the function when it is invoked
- kwargs (dict) Dictionary of keyword arguments to be passed to the function when it is invoked
- **n** (int) Generation count. Incremented whenever the task is based on a previous task (i.e. it is a rescheduled task)

#### regenerateAndDeprecate()

Sets the deleted flag of this task to True, and returns a new task the same as this one but not deleted and with the scheduled time 'when' recalculated from the clock

Here are some details on parts of the internal implementation of aspects of this library.

• modindex | Full Index

This collection of Python modules provides clients and servers for the network protocols defined in the DVB "Companion Screens and Streams" (CSS) specification ETSI 103 286 part 2. There are also supporting classes that model clocks (e.g. to represent timelines) and their inter-relationships.

Use it to build clients and servers for each of the protocols (CSS-WC, CSS-CII and CSS-TS) that mock or simulate the roles of TV Devices and Companion Screen Applications for testing and prototyping.

To use this library you need to have a working understanding of these protocols and, of course, the Python programming language.

		n Screen Synchro	

# CHAPTER 5

# Getting started

- 1. Install, following the instructions in the README.
- 2. Try to Run the examples.
- 3. Read the docs for the DVB CSS Protocol modules.
- 4. Use the library in you own code

"pydvbcss - a library implementing DVB protocols for Companion Screen Synchronisation, Release 0.4.1-release	

CHAP <sup>-</sup>		h
	1 L I 1	$\mathbf{\mathcal{O}}$

# State of implementation

This library does not currently implement the CSS-TE or CSS-MRS protocols (from the DVB specification).

There are some unit tests but these mainly only cover the calculations done within clock objects and the packing and unpacking of JSON messages.

"pydvbcss - a library implementing DVB protocols for Companion Screen Synchronisation, Release 0.4.1-release			

			_
CL	1Λ	DT	o /
(,	17	ГΙ	7 <i>I</i>

## Upgrading from previous versions

See the release notes / change log for details of what is new in this version of pydvbcss.

	enting DVB protocol		

# CHAPTER 8

#### License and Contributing

pydvbcss is licensed as open source software under the terms of the Apache License v2.0.

See the *CONTRIBUTING* and *AUTHORS* files for information on how to contribute and who has contributed to this library.

	enting DVB protocol		

CHAPTER	₹9
---------	----

Contact and discuss

There is a pydvbcss google group for announcements and discussion of this library.

'pydvbcss - a library implementing DVB protocols for Companion Screen Synchron Release 0.4.1-release	isation,

### Python Module Index

#### d

```
dvbcss.clock, 57
dvbcss.monotonic_time, 55
dvbcss.protocol, 7
dvbcss.protocol.cii, 11
dvbcss.protocol.client.cii, 16
dvbcss.protocol.client.ts, 29
dvbcss.protocol.client.wc,44
dvbcss.protocol.client.wc.algorithm, 44
dvbcss.protocol.server,95
dvbcss.protocol.server.cii,22
dvbcss.protocol.server.ts, 36
dvbcss.protocol.server.wc,52
dvbcss.protocol.ts, 24
dvbcss.protocol.wc, 39
dvbcss.task,91
е
examples, 1
examples.CIIClient, 5
examples.CIIServer, 5
examples.TSClient, 6
examples. TSS erver, 6
examples.TVDevice, 7
examples.WallClockClient, 4
examples.WallClockServer,4
```

"pydvbcss - a library implementing DVB protocols for Companion Screen Synchronisation, Release 0.4.1-release

112 Python Module Index

Symbols WebSocketHandler (class in dvbcss.protocol.server), 96 _Scheduler (class in dvbcss.task), 98 _Task (class in dvbcss.task), 99	calcWhen() (dvbcss.clock.TunableClock method), 81 canAllocateConnection()
4	checkCandidate() (dvbcss.protocol.client.wc.algorithmfilterpredict.
accuracy (dvbcss.protocol.cii.TimelineOption attribute), 15 actual (dvbcss.protocol.ts.AptEptLpt attribute), 29 addCandidate() (dvbcss.protocol.client.wc.algorithmfilten method), 48 adjustTicks() (dvbcss.clock.TunableClock method), 81 algorithm (dvbcss.protocol.client.wc.WallClockClient at- tribute), 49 algorithm() (dvbcss.protocol.client.wc.algorithm. method), 46 allProperties() (dvbcss.protocol.cii.CII class method), 14 AptEptLpt (class in dvbcss.protocol.ts), 28	method), 48 childTicks (dvbcss.clock.Correlation attribute), 90 CII (class in dvbcss.protocol.cii), 12 cii (dybcss.protocol.client.cii.CIIClient attribute), 18 PCIIClient (class in dvbcss.protocol.client.cii), 18 CIIClientConnection (class in dvbcss.protocol.client.cii), 21 ClockBase (class in dvbcss.clock), 64 clockDiff() (dvbcss.clock.ClockBase method), 64 clockDiff() (dvbcss.clock.CorrelatedClock method), 73 clockDiff() (dvbcss.clock.OffsetClock method), 77 clockDiff() (dvbcss.clock.RangeCorrelatedClock
B	method), 86 clockDiff() (dvbcss.clock.SysClock method), 68
pind() (dvbcss.clock.ClockBase method), 64 pind() (dvbcss.clock.CorrelatedClock method), 72 pind() (dvbcss.clock.OffsetClock method), 77 pind() (dvbcss.clock.RangeCorrelatedClock method), 86 pind() (dvbcss.clock.SysClock method), 67 pind() (dvbcss.clock.TunableClock method), 81 putWith() (dvbcss.clock.Correlation method), 90	clockDiff() (dvbcss.clock.TunableClock method), 81 combine() (dvbcss.protocol.cii.CII method), 14 connect() (dvbcss.protocol.client.cii.CIIClient method), 19 connect() (dvbcss.protocol.client.cii.CIIClientConnection method), 21 connect() (dvbcss.protocol.client.ts.TSClientClockController method), 35 connect() (dvbcss.protocol.client.ts.TSClientConnection
calcCorrelationFor() (dvbcss.protocol.wc.Candidate	method), 33
method), 43	connected (dvbcss.protocol.client.cii.CIIClient attribute), 18
calcQuality() (in module dvbcss.protocol.client.wc.algorithm), 52 calcWhen() (dvbcss.clock.ClockBase method), 64 calcWhen() (dvbcss.clock.CorrelatedClock method), 73 calcWhen() (dvbcss.clock.OffsetClock method), 77 calcWhen() (dvbcss.clock.RangeCorrelatedClock method), 86	connected (dvbcss.protocol.client.cii.CIIClientConnection attribute), 21 connected (dvbcss.protocol.client.ts.TSClientClockController attribute), 35 connected (dvbcss.protocol.client.ts.TSClientConnection attribute), 33 ConnectionError (class in dvbcss.protocol.client), 54
calcWhen() (dvbcss.clock.SysClock method), 67	contentId (dybess protocol cii CII attribute) 13

contentIdStatus (dvbcss.protocol.cii.CII attribute), 13 contentIdStem (dvbcss.protocol.ts.SetupData attribute), 27 contentTime (dvbcss.protocol.ts.Timestamp attribute), 29 ControlTimestamp (class in dvbcss.protocol.ts), 27 copy() (dvbcss.protocol.cii.CII method), 14	dvbcss.protocol.server.ts (module), 36 dvbcss.protocol.server.wc (module), 52 dvbcss.protocol.ts (module), 24 dvbcss.protocol.wc (module), 39 dvbcss.task (module), 91
copy() (dvbcss.protocol.ts.AptEptLpt method), 29	E
copy() (dvbcss.protocol.ts.Aptept.pr method), 29 copy() (dvbcss.protocol.ts.ControlTimestamp method), 28 copy() (dvbcss.protocol.ts.SetupData method), 27	earliest (dvbcss.protocol.ts.AptEptLpt attribute), 29 earliestClock (dvbcss.protocol.client.ts.TSClientClockController
copy() (dvbcss.protocol.wc.WCMessage method), 41 CorrelatedClock (class in dvbcss.clock), 71	attribute), 35 encode() (dvbcss.protocol.cii.TimelineOption class method), 16
Correlation (class in dvbcss.clock), 90	encodePrecision() (dvbcss.protocol.wc.WCMessage class
correlation (dvbcss.clock,CorrelatedClock attribute), 73	method), 41
correlation (dvbcss.clock.TunableClock attribute), 81	errorGrowthRate (dvbcss.clock.Correlation attribute), 91
correlation1 (dvbcss.clock.RangeCorrelatedClock at-	examples (module), 1
tribute), 87	examples.CIIClient (module), 5
correlation2 (dvbcss.clock.RangeCorrelatedClock at-	examples.CIIServer (module), 5
tribute), 87	examples.TSClient (module), 6
	examples.TSServer (module), 6
D	examples.TVDevice (module), 7
decode() (dvbcss.protocol.cii.TimelineOption class	examples.WallClockClient (module), 4
method), 15	examples.WallClockServer (module), 4
definedProperties() (dvbcss.protocol.cii.CII method), 14	
diff() (dvbcss.protocol.cii.CII class method), 14	F
disconnect() (dvbcss.protocol.client.cii.CIIClient	FilterAndPredict() (in module
method), 19	dybcss.protocol.client.wc.algorithm), 52
disconnect()  (dvbcss.protocol.client.cii.CIIClientConnection)  and  better a connection of the c	<sup>n</sup> FilterLowestDispersionCandidate (class in
method), 21	dvbcss.protocol.client.wc.algorithmfilterpredict),
$disconnect () \ (dvbcss.protocol.client.ts. TSC lient Clock Contract () $	oller 51
method), 35	FilterRttThreshold (class in
disconnect() (dvbcss.protocol.client.ts.TSClientConnection method), 33	dvbcss.protocol.client.wc.algorithmfilterpredict), 51
dispersionAtTime() (dvbcss.clock.ClockBase method), 64	fromParentTicks() (dvbcss.clock.ClockBase method), 64 fromParentTicks() (dvbcss.clock.CorrelatedClock
dispersionAtTime() (dvbcss.clock.CorrelatedClock	method), 73
method), 73	fromParentTicks() (dvbcss.clock.OffsetClock method),
$dispersion At Time () \ (dvbcss.clock.Offset Clock \ method),$	78
78	fromParentTicks() (dvbcss.clock.RangeCorrelatedClock
dispersionAtTime() (dvbcss.clock.RangeCorrelatedClock	method), 87
method), 87	fromParentTicks() (dvbcss.clock.SysClock method), 68
dispersionAtTime() (dvbcss.clock.SysClock method), 68	fromParentTicks() (dvbcss.clock.TunableClock method),
dispersionAtTime() (dvbcss.clock.TunableClock	81
method), 81 dvbcss.clock (module), 57	fromRootTicks() (dvbcss.clock.ClockBase method), 65
dvbcss.monotonic_time (module), 55	fromRootTicks() (dvbcss.clock.CorrelatedClock
dvbcss.protocol (module), 7	method), 73
dvbcss.protocol.cii (module), 11	fromRootTicks() (dvbcss.clock.OffsetClock method), 78
dvbcss.protocol.cli (module), 11 dvbcss.protocol.client.cii (module), 16	fromRootTicks() (dvbcss.clock.RangeCorrelatedClock
dvbcss.protocol.client.ts (module), 29	method), 87 fromRootTicks() (dvbcss.clock.SysClock method), 68
dvbcss.protocol.client.wc (module), 44	fromRootTicks() (dvbcss.clock.SysClock method), 68 fromRootTicks() (dvbcss.clock.TunableClock method),
dvbcss.protocol.client.wc.algorithm (module), 44	
	82
dvbcss.protocol.server (module), 95	82

G	$getStatusSummary () \ (dvbcss.protocol.client.ts. TSC lientClockController$
getAncestry() (dvbcss.clock.ClockBase method), 65	method), 35
getAncestry() (dvbcss.clock.CorrelatedClock method), 74	getWorstDispersion() (dvbcss.protocol.client.wc.algorithm.LowestDispersion method), 50
getAncestry() (dvbcss.clock.OffsetClock method), 78	1
getAncestry() (dvbcss.clock.RangeCorrelatedClock	ı
method), 87	id() (dvbcss.protocol.serverWebSocketHandler method),
getAncestry() (dvbcss.clock.SysClock method), 68	97
getAncestry() (dvbcss.clock.TunableClock method), 82	initialError (dvbcss.clock.Correlation attribute), 91
getCurrentDispersion() (dvbcss.protocol.client.wc.algorithm	ni. Axvielators perfect of the control of the contr
method), 50	isAvailable() (dvbcss.clock.CorrelatedClock method), 74
getCurrentDispersion() (dvbcss.protocol.client.wc.algorithm	ni.MosiRelent (dvbcss.clock.OffsetClock method), 79
method), 51	isAvailable() (dvbcss.clock.RangeCorrelatedClock
getEffectiveSpeed() (dvbcss.clock.ClockBase method),	method), 88
65	isAvailable() (dvbcss.clock.SysClock method), 69
getEffectiveSpeed() (dvbcss.clock.CorrelatedClock	isAvailable() (dvbcss.clock.TunableClock method), 82
method), 74	isChangeSignificant() (dvbcss.clock.CorrelatedClock
getEffectiveSpeed() (dvbcss.clock.OffsetClock method),	method), 74
78	isChangeSignificant() (dvbcss.clock.TunableClock
getEffectiveSpeed() (dvbcss.clock.RangeCorrelatedClock	method), 83
method), 87	isEnabled() (dvbcss.protocol.serverWebSocketHandler
getEffectiveSpeed() (dvbcss.clock.SysClock method), 68	class method), 97
getEffectiveSpeed() (dvbcss.clock.TunableClock	isNanos (dvbcss.protocol.wc.Candidate attribute), 43
method), 82	
getMaxFreqError() (dvbcss.protocol.wc.WCMessage	L
method), 41	latest (dvbcss.protocol.ts.AptEptLpt attribute), 29
getParent() (dvbcss.clock.ClockBase method), 65	latestCII (dvbcss.protocol.client.cii.CIIClient attribute),
getParent() (dvbcss.clock.CorrelatedClock method), 74	18
getParent() (dvbcss.clock.OffsetClock method), 78	latestClock (dvbcss.protocol.client.ts.TSClientClockController
getParent() (dvbcss.clock.RangeCorrelatedClock	attribute), 35
method), 87	latestCt (dvbcss.protocol.client.ts.TSClientClockController
getParent() (dvbcss.clock.SysClock method), 68	attribute), 35
getParent() (dvbcss.clock.TunableClock method), 82	LowestDispersionCandidate (class in
getPrecision() (dvbcss.protocol.wc.WCMessage method),	dvbcss.protocol.client.wc.algorithm), 49
41	
getRoot() (dvbcss.clock.ClockBase method), 65	M
getRoot() (dvbcss.clock.CorrelatedClock method), 74	maxFreqError (dvbcss.protocol.wc.Candidate attribute),
getRoot() (dvbcss.clock.OffsetClock method), 78	43
<pre>getRoot() (dvbcss.clock.RangeCorrelatedClock method),</pre>	maxFreqError (dvbcss.protocol.wc.WCMessage at-
87	tribute), 41
getRoot() (dvbcss.clock.SysClock method), 68	measurePrecision() (in module dvbcss.clock), 64
getRoot() (dvbcss.clock.TunableClock method), 82	MostRecent (class in dvbcss.protocol.client.wc.algorithm),
getRootMaxFreqError() (dvbcss.clock.ClockBase	50
method), 65	mrsUrl (dvbcss.protocol.cii.CII attribute), 13
getRootMaxFreqError() (dvbcss.clock.CorrelatedClock	msg (dvbcss.protocol.wc.Candidate attribute), 43
method), 74	msgtype (dvbcss.protocol.wc.WCMessage attribute), 40
getRootMaxFreqError() (dvbcss.clock.OffsetClock	moge, po (a room, protocol, me, m emicosage autitoute), 40
method). 78	N
getRootMaxFreqError() (dvbcss.clock.RangeCorrelatedClo	ock
method), 88	nanos (uvdess.cioek.cioek.base attribute), 65
getRootMaxFreqError() (dvbcss.clock.SysClock	nanos (dvbcss.clock.CorrelatedClock attribute), 74
method), 69	nanos (dvbcss.clock.OffsetClock attribute), 79
getRootMaxFreqError() (dvbcss.clock.TunableClock	nanos (dvbcss.clock.RangeCorrelatedClock attribute), 88
method) 82	nanos (dvbcss.clock.SysClock attribute), 69

nanos (dvbcss.clock.TunableClock attribute), 83 nanosToTicks() (dvbcss.clock.ClockBase method), 65	onMrsUrlChange() (dvbcss.protocol.client.cii.CIIClient method), 19
nanosToTicks() (dvbcss.clock.CorrelatedClock method), 75	onPresentationStatusChange() (dvbcss.protocol.client.cii.CIIClient method),
nanosToTicks() (dvbcss.clock.OffsetClock method), 79	20
nanosToTicks() (dvbcss.clock.RangeCorrelatedClock	onPrivateChange() (dvbcss.protocol.client.cii.CIIClient
method), 88	method), 20
nanosToTicks() (dvbcss.clock.SysClock method), 69	onProtocolError() (dvbcss.protocol.client.cii.CIIClient
nanosToTicks() (dvbcss.clock.TunableClock method), 83	method), 20
notify() (dvbcss.clock.ClockBase method), 66	$on Protocol Error () \ (dvbcss.protocol.client.cii. CIIC lient Connection$
notify() (dvbcss.clock.CorrelatedClock method), 75	method), 21
notify() (dvbcss.clock.OffsetClock method), 79	onProtocolError() (dvbcss.protocol.client.ts.TSClientClockController
notify() (dvbcss.clock.RangeCorrelatedClock method),	method), 35
88	onProtocolError() (dvbcss.protocol.client.ts.TSClientConnection
notify() (dvbcss.clock.SysClock method), 69	method), 33
notify() (dvbcss.clock.TunableClock method), 83 notify() (dvbcss.taskScheduler method), 98	onProtocolVersionChange() (dvbcss.protocol.client.cii.CIIClient method),
	20
O	onTeUrlChange() (dvbcss.protocol.client.cii.CIIClient
offset (dvbcss.clock.OffsetClock attribute), 79	method), 20
offset (dvbcss.protocol.wc.Candidate attribute), 43	onTimelineAvailable() (dvbcss.protocol.client.ts.TSClientClockController
OffsetClock (class in dvbcss.clock), 77	method), 35 onTimelinesChange() (dvbcss.protocol.client.cii.CIIClient
OMIT (in module dvbcss.protocol), 53	method), 20
onChange() (dvbcss.protocol.client.cii.CIIClient method), 19	onTimelineUnavailable()
onCII() (dvbcss.protocol.client.cii.CIIClientConnection	(dvbcss.protocol.client.ts.TSClientClockController
method), 21	method), 36
onCiiReceived() (dvbcss.protocol.client.cii.CIIClient method), 19	onTimingChange() (dvbcss.protocol.client.ts.TSClientClockController method), 36
onClockAdjusted() (dvbcss.protocol.client.wc.algorithm.Lomethod), 50	we Tri Vis Change and debess.protocol.client.cii.CIIClient method), 20
onConnected() (dvbcss.protocol.client.cii.CIIClient method), 19	onWcUrlChange() (dvbcss.protocol.client.cii.CIIClient method), 20
on Connected ()  (dvbcss.protocol.client.cii. CIIC lient Connected ()  (dvbcss.protocol.client.cii.)  (dvbcss.protocol.cl	RegiginalOriginate (dvbcss.protocol.wc.WCMessage at-
method), 21	tribute), 41 periginateNanos (dvbcss.protocol.wc.WCMessage at-
onConnected() (dvbcss.protocol.client.ts.TSClientClockConnected(), 35	tribute), 41
on Connected ()  (dvbcss.protocol.client.ts. TSC lient Connecti	OB
method), 33	
$on Content Id Change () \ (dvbcss.protocol.client.cii. CIIC lient$	
method), 19	pack() (dvbcss.protocol.cii.TimelineOption method), 16
onContentIdStatusChange()	pack() (dvbcss.protocol.ts.AptEptLpt method), 29
(dvbcss.protocol.client.cii.CIIClient method),	pack() (dvbcss.protocol.ts.ControlTimestamp method), 28
onControlTimestamp() (dvbcss.protocol.client.ts.TSClientC	
method), 33	pack() (dvbcss.protocol.wc.WCMessage method), 41
onDisconnected() (dvbcss.protocol.client.cii.CIIClient	parentTicks (dvbcss.clock.Correlation attribute), 91
method), 19	precision (dvbcss.protocol.wc.Candidate attribute), 43
onDisconnected() (dvbcss.protocol.client.cii.CIIClientConr	
method), 21	predictCorrelation() (dvbcss.protocol.client.wc.algorithmfilterpredict.
$on Disconnected () \ (dvbcss.protocol.client.ts. TSC lient Clock \ and \ an extension of the content of the c$	
method), 35	PredictSimple (class in
onDisconnected() (dvbcss.protocol.client.ts.TSClientConne method), 33	dvbcss.protocol.client.wc.algorithmfilterpredict), 51

presentationStatus (dvbcss.protocol.cii.CII attribute), 13 private (dvbcss.protocol.cii.CII attribute), 14	setParent() (dvbcss.clock.RangeCorrelatedClock method), 88
private (dvbcss.protocol.cii.TimelineOption attribute), 15	setParent() (dvbcss.clock.SysClock method), 69
private (dvbcss.protocol.ts.SetupData attribute), 27	setParent() (dvbcss.clock.TunableClock method), 84
protocolVersion (dvbcss.protocol.cii.CII attribute), 13	setPrecision() (dvbcss.protocol.wc.WCMessage method),
protocol version (avocsos.protocolienien atarioace), 15	41
Q	SetupData (class in dvbcss.protocol.ts), 26
quantifyChange() (dvbcss.clock.CorrelatedClock	sleep() (in module dvbcss.monotonic_time), 57
method), 75	sleepFor() (in module dvbcss.task), 92
quantifyChange() (dvbcss.clock.TunableClock method),	sleepUntil() (in module dvbcss.task), 92
83	slew (dvbcss.clock.TunableClock attribute), 84
П	speed (dvbcss.clock.ClockBase attribute), 66
R	speed (dvbcss.clock.CorrelatedClock attribute), 76
RangeCorrelatedClock (class in dvbcss.clock), 85	speed (dvbcss.clock.OffsetClock attribute), 79
rebaseCorrelationAtTicks()	speed (dvbcss.clock.RangeCorrelatedClock attribute), 88
(dvbcss.clock.CorrelatedClock method),	speed (dvbcss.clock.SysClock attribute), 69
75	speed (dvbcss.clock.TunableClock attribute), 84
rebaseCorrelationAtTicks() (dvbcss.clock.TunableClock method), 83	start() (dvbcss.protocol.client.wc.WallClockClient method), 49
receiveNanos (dvbcss.protocol.wc.WCMessage at-	stop() (dvbcss.protocol.client.wc.WallClockClient
tribute), 41	method), 49
regenerateAndDeprecate() (dvbcss.taskTask method),	stop() (dvbcss.taskScheduler method), 99
99	SysClock (class in dvbcss.clock), 67
rtt (dvbcss.protocol.wc.Candidate attribute), 43	Т
run() (dvbcss.taskScheduler method), 98	
runAt() (in module dvbcss.task), 92	t1 (dvbcss.protocol.wc.Candidate attribute), 42
C	t2 (dvbcss.protocol.wc.Candidate attribute), 42
S	t3 (dvbcss.protocol.wc.Candidate attribute), 42
schedule() (dvbcss.taskScheduler method), 98	t4 (dvbcss.protocol.wc.Candidate attribute), 43
scheduleEvent() (in module dvbcss.task), 92	teUrl (dvbcss.protocol.cii.CII attribute), 13
scheduler (in module dvbcss.task), 97	tickRate (dvbcss.clock.ClockBase attribute), 66
$sendAptEptLpt() \ (dvbcss.protocol.client.ts.TSClientClockCollege \ (dvbcss.protocol.client.ts.TSClient.ts.T$	CTICK RATE (dvbcss.clock.CorrelatedClock attribute), 76
method), 36	tickRate (dvbcss.clock.OffsetClock attribute), 79
sendTimestamp() (dvbcss.protocol.client.ts.TSClientConnemethod), 33	89
setAvailability() (dvbcss.clock.ClockBase method), 66	tickRate (dvbcss.clock.SysClock attribute), 69
setAvailability() (dvbcss.clock.CorrelatedClock method),	tickRate (dvbcss.clock.TunableClock attribute), 84
75	ticks (dvbcss.clock.ClockBase attribute), 66
setAvailability() (dvbcss.clock.OffsetClock method), 79	ticks (dvbcss.clock.CorrelatedClock attribute), 76
setAvailability() (dvbcss.clock.RangeCorrelatedClock	ticks (dvbcss.clock.OffsetClock attribute), 79
method), 88	ticks (dvbcss.clock.RangeCorrelatedClock attribute), 89
setAvailability() (dvbcss.clock.SysClock method), 69	ticks (dvbcss.clock.SysClock attribute), 70
setAvailability() (dvbcss.clock.TunableClock method), 83	ticks (dvbcss.clock.TunableClock attribute), 84
setCorrelationAndSpeed()	time() (in module dvbcss.monotonic_time), 57
(dvbcss.clock.CorrelatedClock method), 75	timelineAvailable (dvbcss.protocol.client.ts.TSClientClockController attribute), 36
setCorrelationAndSpeed() (dvbcss.clock.TunableClock	TimelineOption (class in dvbcss.protocol.cii), 15
method), 84	timelines (dvbcss.protocol.cii.CII attribute), 14
setError() (dvbcss.clock.TunableClock method), 84	timelineSelector (dvbcss.protocol.cii.TimelineOption at-
$set MaxFreqError() \\ \hspace{0.5cm} (dvbcss.protocol.wc.WCMessage$	tribute), 15
method), 41	timelineSelector (dvbcss.protocol.ts.SetupData attribute),
setParent() (dvbcss.clock.ClockBase method), 66	27
setParent() (dvbcss.clock.CorrelatedClock method), 76	timelineSpeedMultiplier (dvbcss.protocol.ts.ControlTimestamp
setParent() (dvbcss.clock.OffsetClock method), 79	attribute), 28

timeMicros() (in module dvbcss.monotonic_time), 57	unbind() (dvbcss.clock.OffsetClock method), 80
timeNanos() (in module dvbcss.monotonic_time), 57	unbind() (dvbcss.clock.RangeCorrelatedClock method)
Timestamp (class in dvbcss.protocol.ts), 29	89
timestamp (dvbcss.protocol.ts.ControlTimestamp at-	unbind() (dvbcss.clock.SysClock method), 70
tribute), 27	unbind() (dvbcss.clock.TunableClock method), 85
toOtherClockTicks() (dvbcss.clock.ClockBase method),	unitsPerSecond (dvbcss.protocol.cii.TimelineOption at
66	tribute), 15
toOtherClockTicks() (dvbcss.clock.CorrelatedClock	unitsPerTick (dvbcss.protocol.cii.TimelineOption at
method), 76	tribute), 15
toOtherClockTicks() (dvbcss.clock.OffsetClock method),	unpack() (dvbcss.protocol.cii.CII class method), 14
80	unpack() (dvbcss.protocol.cii.TimelineOption clas
toOtherClockTicks() (dvbcss.clock.RangeCorrelatedClock	method), 16
method), 89	unpack() (dvbcss.protocol.ts.AptEptLpt class method), 29
toOtherClockTicks() (dvbcss.clock.SysClock method),	unpack() (dvbcss.protocol.ts.ControlTimestamp clas
70	method), 28
toOtherClockTicks() (dvbcss.clock.TunableClock	unpack() (dvbcss.protocol.ts.SetupData class method), 2
method), 84	unpack() (dvbcss.protocol.wc.WCMessage clas
toParentTicks() (dvbcss.clock.ClockBase method), 66	method), 41
toParentTicks() (dvbcss.clock.CorrelatedClock method),	update() (dvbcss.protocol.cii.CII method), 14
76	update() (dvbcss.protocol.en.en method), 14
toParentTicks() (dvbcss.clock.OffsetClock method), 80	W
toParentTicks() (dvbcss.clock.RangeCorrelatedClock	
method), 89	WallClockClient (class in dvbcss.protocol.client.wc), 48
toParentTicks() (dvbcss.clock.SysClock method), 70	wallClockTime (dvbcss.protocol.ts.Timestamp attribute)
toParentTicks() (dvbcss.clock.Sysciock method), 70 toParentTicks() (dvbcss.clock.TunableClock method), 85	29
7.	WCMessage (class in dvbcss.protocol.wc), 40
toRootTicks() (dvbcss.clock.ClockBase method), 67	wcUrl (dvbcss.protocol.cii.CII attribute), 13
toRootTicks() (dvbcss.clock.CorrelatedClock method),	
toRootTicks() (dvbcss.clock.OffsetClock method), 80	
toRootTicks() (dvbcss.clock.RangeCorrelatedClock	
method), 89	
toRootTicks() (dvbcss.clock.SysClock method), 70	
toRootTicks() (dvbcss.clock.TunableClock method), 85	
toTicks() (dvbcss.protocol.wc.Candidate method), 43	
transmitNanos (dvbcss.protocol.wc.WCMessage at-	
tribute), 41	
TSClientClockController (class in	
dvbcss.protocol.client.ts), 34	
TSClientConnection (class in dvbcss.protocol.client.ts),	
32	
tsUrl (dvbcss.protocol.cii.CII attribute), 13	
TunableClock (class in dvbcss.clock), 80	
TYPE_FOLLOWUP (dvbcss.protocol.wc.WCMessage	
attribute), 41	
TYPE_REQUEST (dvbcss.protocol.wc.WCMessage at-	
tribute), 41	
TYPE_RESPONSE (dvbcss.protocol.wc.WCMessage at-	
tribute), 41	
TYPE_RESPONSE_WITH_FOLLOWUP	
(dvbcss.protocol.wc.WCMessage attribute), 41	
11	
U	

unbind() (dvbcss.clock.ClockBase method), 67 unbind() (dvbcss.clock.CorrelatedClock method), 77